

HikCentral Professional Control Client

User Manual

Legal Information

©2021 Hangzhou Hikvision Digital Technology Co., Ltd. All rights reserved.

About this Manual

The Manual includes instructions for using and managing the Product. Pictures, charts, images and all other information hereinafter are for description and explanation only. The information contained in the Manual is subject to change, without notice, due to firmware updates or other reasons. Please find the latest version of this Manual at the Hikvision website (<u>https://www.hikvision.com/</u>).

Please use this Manual with the guidance and assistance of professionals trained in supporting the Product.

Trademarks

HIKVISION and other Hikvision's trademarks and logos are the properties of Hikvision in various jurisdictions.

Other trademarks and logos mentioned are the properties of their respective owners.

Disclaimer

TO THE MAXIMUM EXTENT PERMITTED BY APPLICABLE LAW, THIS MANUAL AND THE PRODUCT DESCRIBED, WITH ITS HARDWARE, SOFTWARE AND FIRMWARE, ARE PROVIDED "AS IS" AND "WITH ALL FAULTS AND ERRORS". HIKVISION MAKES NO WARRANTIES, EXPRESS OR IMPLIED, INCLUDING WITHOUT LIMITATION, MERCHANTABILITY, SATISFACTORY QUALITY, OR FITNESS FOR A PARTICULAR PURPOSE. THE USE OF THE PRODUCT BY YOU IS AT YOUR OWN RISK. IN NO EVENT WILL HIKVISION BE LIABLE TO YOU FOR ANY SPECIAL, CONSEQUENTIAL, INCIDENTAL, OR INDIRECT DAMAGES, INCLUDING, AMONG OTHERS, DAMAGES FOR LOSS OF BUSINESS PROFITS, BUSINESS INTERRUPTION, OR LOSS OF DATA, CORRUPTION OF SYSTEMS, OR LOSS OF DOCUMENTATION, WHETHER BASED ON BREACH OF CONTRACT, TORT (INCLUDING NEGLIGENCE), PRODUCT LIABILITY, OR OTHERWISE, IN CONNECTION WITH THE USE OF THE PRODUCT, EVEN IF HIKVISION HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES OR LOSS.

YOU ACKNOWLEDGE THAT THE NATURE OF THE INTERNET PROVIDES FOR INHERENT SECURITY RISKS, AND HIKVISION SHALL NOT TAKE ANY RESPONSIBILITIES FOR ABNORMAL OPERATION, PRIVACY LEAKAGE OR OTHER DAMAGES RESULTING FROM CYBER-ATTACK, HACKER ATTACK, VIRUS INFECTION, OR OTHER INTERNET SECURITY RISKS; HOWEVER, HIKVISION WILL PROVIDE TIMELY TECHNICAL SUPPORT IF REQUIRED.

YOU AGREE TO USE THIS PRODUCT IN COMPLIANCE WITH ALL APPLICABLE LAWS, AND YOU ARE SOLELY RESPONSIBLE FOR ENSURING THAT YOUR USE CONFORMS TO THE APPLICABLE LAW. ESPECIALLY, YOU ARE RESPONSIBLE, FOR USING THIS PRODUCT IN A MANNER THAT DOES NOT INFRINGE ON THE RIGHTS OF THIRD PARTIES, INCLUDING WITHOUT LIMITATION, RIGHTS OF PUBLICITY, INTELLECTUAL PROPERTY RIGHTS, OR DATA PROTECTION AND OTHER PRIVACY RIGHTS. YOU SHALL NOT USE THIS PRODUCT FOR ANY PROHIBITED END-USES, INCLUDING THE DEVELOPMENT OR PRODUCTION OF WEAPONS OF MASS DESTRUCTION, THE DEVELOPMENT OR PRODUCTION OF CHEMICAL OR BIOLOGICAL WEAPONS, ANY ACTIVITIES IN THE CONTEXT RELATED TO ANY NUCLEAR EXPLOSIVE OR UNSAFE NUCLEAR FUEL-CYCLE, OR IN SUPPORT OF HUMAN RIGHTS ABUSES.

IN THE EVENT OF ANY CONFLICTS BETWEEN THIS MANUAL AND THE APPLICABLE LAW, THE LATTER PREVAILS.

Symbol Conventions

The symbols that may be found in this document are defined as follows.

Symbol	Description
A Danger	Indicates a hazardous situation which, if not avoided, will or could result in death or serious injury.
A Caution	Indicates a potentially hazardous situation which, if not avoided, could result in equipment damage, data loss, performance degradation, or unexpected results.
III Note	Provides additional information to emphasize or supplement important points of the main text.

Contents

Chapter 1 About Control Client 1
Chapter 2 Login 2
2.1 First Time Login 2
2.2 Normal Login (Not First Time) 3
2.3 Change Password for Reset User and Login 5
Chapter 3 Home Page Overview
3.1 Customize Control Panel 12
3.2 Customize Navigation Bar 14
Chapter 4 Manage View 16
Chapter 5 Live View 18
5.1 Start Live View in Area Mode 19
5.2 Start Live View in View Mode 20
5.3 Auto-Switch Cameras in an Area 21
5.4 PTZ Control 22
5.4.1 Configure Preset 24
5.4.2 Configure Patrol 25
5.4.3 Configure Pattern 26
5.5 Manual Recording and Capture 27
5.5.1 Manual Recording 27
5.5.2 View Manually Recorded Videos 28
5.5.3 Capture Pictures 29
5.5.4 View Captured Pictures
5.6 View Dewarped Live View of Fisheye Camera 31
5.7 View People Density in Live View 33
5.8 Perform Manual Panorama Tracking 35
5.9 Create Zooming Area to View Detailed Live View

5.10 View Detected Event in Live View	8
5.11 More Functions 4	10
5.12 Customize Icons on Live View Window 4	10
hapter 6 Real-Time Temperature and People Counting Monitoring	4
hapter 7 Start a Roll Call 4	6
hapter 8 Playback	8
8.1 Normal Playback 4	8
8.1.1 Search Video File 4	8
8.1.2 Play Video File 4	19
8.2 Start Playback in View Mode 4	19
8.3 Synchronous Playback	50
8.4 Fisheye Playback	51
8.5 Create Zooming Area to View Detailed Playback5	51
8.6 Customize Icons on Playback Window5	53
hapter 9 Visual Tracking	57
hapter 9 Visual Tracking59.1 Perform Visual Tracking in Live View5	
	57
9.1 Perform Visual Tracking in Live View	57 58
9.1 Perform Visual Tracking in Live View	57 58 5 1
9.1 Perform Visual Tracking in Live View	57 58 51 53
9.1 Perform Visual Tracking in Live View	57 58 51 53 54
9.1 Perform Visual Tracking in Live View 5 9.2 View Visual Tracking Video 5 hapter 10 Manage Favorites 6 hapter 11 Add Web Page to Display Window 6 hapter 12 Customize Intelligent Monitoring Contents 6	57 58 51 53 54 58
9.1 Perform Visual Tracking in Live View 5 9.2 View Visual Tracking Video 5 hapter 10 Manage Favorites 6 hapter 11 Add Web Page to Display Window 6 hapter 12 Customize Intelligent Monitoring Contents 6 hapter 13 Video Search 6	57 58 51 53 54 58
9.1 Perform Visual Tracking in Live View 5 9.2 View Visual Tracking Video 5 hapter 10 Manage Favorites 6 hapter 11 Add Web Page to Display Window 6 hapter 12 Customize Intelligent Monitoring Contents 6 hapter 13 Video Search 6 13.1 Search Video Footages by Time Range 6	57 58 51 53 54 58 58 72
9.1 Perform Visual Tracking in Live View 5 9.2 View Visual Tracking Video 5 hapter 10 Manage Favorites 6 hapter 11 Add Web Page to Display Window 6 hapter 12 Customize Intelligent Monitoring Contents 6 hapter 13 Video Search 6 13.1 Search Video Footages by Time Range 6 13.2 Search Tagged Video Footages 7	57 58 51 53 54 58 58 72 74
9.1 Perform Visual Tracking in Live View 5 9.2 View Visual Tracking Video 5 hapter 10 Manage Favorites 6 hapter 11 Add Web Page to Display Window 6 hapter 12 Customize Intelligent Monitoring Contents 6 hapter 13 Video Search 6 13.1 Search Video Footages by Time Range 6 13.2 Search Tagged Video Footages 7 13.3 Search Locked Video Footages 7	57 58 51 53 54 58 58 72 74 77
9.1 Perform Visual Tracking in Live View 5 9.2 View Visual Tracking Video 5 hapter 10 Manage Favorites 6 hapter 11 Add Web Page to Display Window 6 hapter 12 Customize Intelligent Monitoring Contents 6 hapter 13 Video Search 6 13.1 Search Video Footages by Time Range 6 13.2 Search Tagged Video Footages 7 13.3 Search Locked Video Footages 7 13.4 Search Video/Picture/Audio Stored on Dock Station 7	57 58 51 53 54 58 72 74 77 78

Chapter 14 Manage Downloading Tasks85
Chapter 15 Map Management 87
15.1 Operate Hot Spot 87
15.1.1 Preview Hot Spot 87
15.1.2 Arm or Disarm Hot Spot 89
15.1.3 View History Alarm 89
15.1.4 Broadcast via Hot Spot 89
15.2 Preview Hot Region 91
15.3 Preview Resource Group 91
15.4 View Remote Site Alarm 92
15.5 Operate Map 93
Chapter 16 Access Control and Elevator Control 95
16.1 Control Door Status in Live View95
16.2 Control Floor Status in Live View
16.3 Search Access Records 101
16.4 Search Data Recorded on Device 104
16.5 Open Door for Multi-Factor Authentication 105
16.6 Handle Opening Door Request from Video Access Control Terminal 107
16.7 Perform Entry & Exit Counting 108
Chapter 17 Video Intercom 110
17.1 Control Door Status in Live View 110
17.2 Call Indoor Station 112
17.3 Answer Call 113
Chapter 18 Vehicle 115
18.1 View ANPR Camera's Live Video 115
18.2 View UVSS's Live Video 117
18.3 Entrance & Exit Control 119
18.3.1 View Passing Vehicle Information 120

18.3.2 Automatically Open Barrier for Vehicles	123
18.3.3 Manually Open Barrier for Vehicles	126
18.3.4 Correct License Plate Number	129
18.3.5 Manually Control Barrier	130
18.3.6 Hand Over Shifts	131
18.4 Parking Space Monitoring	133
18.5 Add Recognized Vehicle to Vehicle List	134
18.6 Vehicle and Record Search	137
18.6.1 Search for Vehicle Passing Records	138
18.6.2 Search for Payment Records	140
18.6.3 Search for Parked Vehicles	141
18.6.4 Search for Parking Records	144
18.6.5 Search for Multiple Vehicles Under One Account Status	146
Chapter 19 Mobile Monitoring	148
19.1 Driving Monitoring	148
19.1 Driving Monitoring	152
19.1 Driving Monitoring 19.2 Mobile Monitoring Record	152 152
 19.1 Driving Monitoring 19.2 Mobile Monitoring Record 19.2.1 Search for Vehicle Routes 	152 152 153
 19.1 Driving Monitoring 19.2 Mobile Monitoring Record 19.2.1 Search for Vehicle Routes 19.2.2 Search for Driving Events 	152 152 153 155
 19.1 Driving Monitoring 19.2 Mobile Monitoring Record 19.2.1 Search for Vehicle Routes 19.2.2 Search for Driving Events Chapter 20 Face and Body Recognition 	152 152 153 155 155
 19.1 Driving Monitoring 19.2 Mobile Monitoring Record 19.2.1 Search for Vehicle Routes 19.2.2 Search for Driving Events Chapter 20 Face and Body Recognition 20.1 View Detected and Matched Face in Live View 	152 152 153 155 155 157
 19.1 Driving Monitoring 19.2 Mobile Monitoring Record 19.2.1 Search for Vehicle Routes	152 153 155 155 157 160
 19.1 Driving Monitoring	152 153 155 155 157 160 160
 19.1 Driving Monitoring	152 153 155 155 157 160 160 165
 19.1 Driving Monitoring	152 153 155 155 157 160 160 165 168
 19.1 Driving Monitoring	152 153 155 155 157 160 165 168 171

20.4.2 Search Human Body Pictures by Picture 1	.76
20.5 Archive Search 1	.80
20.6 Identity Verification 1	.82
20.6.1 Compare with Face Comparison Group 1	.82
20.6.2 Compare with Specific Picture 1	.83
Chapter 21 Security Control 1	.86
21.1 Start Live View of Radar's Calibrated Camera1	.86
21.2 Perform Arming Control for Resources 1	.87
21.3 Handle Panic Alarm from Panic Alarm Station1	.89
Chapter 22 Check Alarm and Event 1	.91
22.1 View Resources' Real-Time Alarms 1	.91
22.2 View Pop-up Window Triggered by Alarm 1	.96
22.3 Manually Trigger User-Defined Event 1	.98
22.4 Perform Arming Control for Alarms 19	99
22.5 Event and Alarm Search	
	201
22.5 Event and Alarm Search 20	201 201
22.5 Event and Alarm Search 2 22.5.1 Alarm Overview 2	201 201 202
22.5 Event and Alarm Search 2 22.5.1 Alarm Overview 2 22.5.2 Search Event and Alarm Logs 2	201 201 202 205
22.5 Event and Alarm Search 20 22.5.1 Alarm Overview 20 22.5.2 Search Event and Alarm Logs 20 Chapter 23 Evidence Management Center	201 201 202 205 205
22.5 Event and Alarm Search 20 22.5.1 Alarm Overview 20 22.5.2 Search Event and Alarm Logs 20 Chapter 23 Evidence Management Center 20 23.1 Save Found Video Footage as Evidence 20	201 201 202 205 205 208
22.5 Event and Alarm Search2022.5.1 Alarm Overview2022.5.2 Search Event and Alarm Logs20Chapter 23 Evidence Management Center23.1 Save Found Video Footage as Evidence2023.2 Save Manually Recorded Video as Evidence in Live View20	201 202 205 205 208 208
22.5 Event and Alarm Search2422.5.1 Alarm Overview2422.5.2 Search Event and Alarm Logs24Chapter 23 Evidence Management Center2423.1 Save Found Video Footage as Evidence2423.2 Save Manually Recorded Video as Evidence in Live View2423.3 Save Clipped Video as Evidence in Playback24	201 201 202 205 205 208 208 208
22.5 Event and Alarm Search2122.5.1 Alarm Overview2122.5.2 Search Event and Alarm Logs21Chapter 23 Evidence Management Center2123.1 Save Found Video Footage as Evidence2123.2 Save Manually Recorded Video as Evidence in Live View2123.3 Save Clipped Video as Evidence in Playback2123.4 Save Downloaded Video Footage as Evidence21	201 202 205 205 208 208 208 208 209 210
22.5 Event and Alarm Search2422.5.1 Alarm Overview2422.5.2 Search Event and Alarm Logs2423.1 Save Found Video Footage as Evidence2423.2 Save Manually Recorded Video as Evidence in Live View2423.3 Save Clipped Video as Evidence in Playback2423.4 Save Downloaded Video Footage as Evidence2423.5 Add Evidence24	201 201 202 205 205 208 208 208 208 209 210
22.5 Event and Alarm Search222.5.1 Alarm Overview222.5.2 Search Event and Alarm Logs223.1 Save Found Video Footage as Evidence223.2 Save Manually Recorded Video as Evidence in Live View223.3 Save Clipped Video as Evidence in Playback223.4 Save Downloaded Video Footage as Evidence223.5 Add Evidence223.6 Manage Unlinked Files2	201 201 202 205 205 208 208 208 208 209 210 212
22.5 Event and Alarm Search2122.5.1 Alarm Overview2122.5.2 Search Event and Alarm Logs21Chapter 23 Evidence Management Center2123.1 Save Found Video Footage as Evidence2123.2 Save Manually Recorded Video as Evidence in Live View2123.3 Save Clipped Video as Evidence in Playback2123.4 Save Downloaded Video Footage as Evidence2123.5 Add Evidence2123.6 Manage Unlinked Files223.6.1 Add and View Unlinked Files2	201 201 202 205 205 208 208 208 208 209 210 212 213 214

24.1 Manage Smart Wall (Decoding Device) 2	.17
24.1.1 Decode and Display Directly 2	21
24.1.2 View Settings 2	23
24.1.3 Set View Auto-Switch Interval 2	25
24.1.4 Auto-Switch Cameras in One Window 2	26
24.1.5 Auto-Switch Cameras in Multiple Windows 2	27
24.1.6 Create a Roaming Window 2	28
24.1.7 View Alarm's Related Video on Smart Wall 2	29
24.1.8 View and Export Window No. and Camera ID 2	30
24.2 Manage Smart Wall (Graphic Card) 2	30
24.2.1 Display Contents on Smart Wall in Smart Wall Mode	31
24.2.2 Display Contents on Smart Wall in Live View Mode	32
24.2.3 Display Alarm's Related Video on Smart Wall 2	36
24.2.4 Display Health Monitoring Page on Smart Wall 2	38
24.2.5 Display Desktop on Smart Wall 2	39
24.2.5 Display Desktop on Smart Wall 2	41
24.2.5 Display Desktop on Smart Wall 2 Chapter 25 Broadcast	41 41
24.2.5 Display Desktop on Smart Wall 2 Chapter 25 Broadcast 2 25.1 Broadcast to Connected Speaker Unit 2	2 41 241 242
24.2.5 Display Desktop on Smart Wall 2 Chapter 25 Broadcast 2 25.1 Broadcast to Connected Speaker Unit 2 25.2 Broadcast to Connected Devices 2	2 41 241 242 242
24.2.5 Display Desktop on Smart Wall 2 Chapter 25 Broadcast 2 25.1 Broadcast to Connected Speaker Unit 2 25.2 Broadcast to Connected Devices 2 25.3 Search for Live Broadcast Records 2	2 41 242 242 242
24.2.5 Display Desktop on Smart Wall 2 Chapter 25 Broadcast 2 25.1 Broadcast to Connected Speaker Unit 2 25.2 Broadcast to Connected Devices 2 25.3 Search for Live Broadcast Records 2 Chapter 26 Intelligent Analysis Report 2	241 242 242 242 244
24.2.5 Display Desktop on Smart Wall2Chapter 25 Broadcast225.1 Broadcast to Connected Speaker Unit225.2 Broadcast to Connected Devices225.3 Search for Live Broadcast Records2Chapter 26 Intelligent Analysis Report226.1 Customize Report Dashboard2	241 242 242 244 244 245
24.2.5 Display Desktop on Smart Wall2Chapter 25 Broadcast225.1 Broadcast to Connected Speaker Unit225.2 Broadcast to Connected Devices225.3 Search for Live Broadcast Records2Chapter 26 Intelligent Analysis Report226.1 Customize Report Dashboard226.2 Generate People Counting Report2	241 242 242 244 244 245 248
24.2.5 Display Desktop on Smart Wall2Chapter 25 Broadcast225.1 Broadcast to Connected Speaker Unit225.2 Broadcast to Connected Devices225.3 Search for Live Broadcast Records2Chapter 26 Intelligent Analysis Report226.1 Customize Report Dashboard226.2 Generate People Counting Report226.3 Generate People Density Analysis Report2	241 242 242 244 244 245 248 252
24.2.5 Display Desktop on Smart Wall2Chapter 25 Broadcast225.1 Broadcast to Connected Speaker Unit225.2 Broadcast to Connected Devices225.3 Search for Live Broadcast Records226.1 Customize Report Dashboard226.2 Generate People Counting Report226.3 Generate People Density Analysis Report226.4 Generate Queue Analysis Report2	241 242 242 244 244 245 248 255
24.2.5 Display Desktop on Smart Wall2Chapter 25 Broadcast225.1 Broadcast to Connected Speaker Unit225.2 Broadcast to Connected Devices225.3 Search for Live Broadcast Records225.3 Search for Live Broadcast Records2Chapter 26 Intelligent Analysis Report226.1 Customize Report Dashboard226.2 Generate People Counting Report226.3 Generate People Density Analysis Report226.4 Generate Queue Analysis Report226.5 Generate Heat Analysis Report226.6 Generate Pathway Analysis Report226.6 Generate Pathway Analysis Report2	241 242 242 244 244 245 248 255

26.9 Generate Vehicle Analysis Report	
26.10 Generate Skin-Surface Temperature Analysis Repo	rt 269
Chapter 27 Maintenance	272
27.1 Health Monitoring	272
27.1.1 Real-Time Health Status Overview	
27.1.2 Real-Time Health Status Overview (Topology)	275
27.1.3 Historical Health Data Overview	283
27.2 Resource Status	285
27.3 Log Search	293
27.3.1 Search for Server Logs	293
27.3.2 Search for Online/Offline Logs of Device	295
27.3.3 Search for Logs Stored on Device	296
27.3.4 Search for Online/Offline Logs of Resource	297
27.3.5 Search for Recording Status of Resource	299
Chapter 28 Tools	
Chapter 28 Tools	
•	
28.1 Play Video via VSPlayer	
28.1 Play Video via VSPlayer 28.2 Perform Two-Way Audio	
28.1 Play Video via VSPlayer 28.2 Perform Two-Way Audio 28.3 Broadcast to Connected Devices	
28.1 Play Video via VSPlayer 28.2 Perform Two-Way Audio 28.3 Broadcast to Connected Devices 28.4 Control Alarm Output	
28.1 Play Video via VSPlayer 28.2 Perform Two-Way Audio 28.3 Broadcast to Connected Devices 28.4 Control Alarm Output 28.5 Record Screen	
28.1 Play Video via VSPlayer 28.2 Perform Two-Way Audio 28.3 Broadcast to Connected Devices 28.4 Control Alarm Output 28.5 Record Screen Chapter 29 System Settings	
28.1 Play Video via VSPlayer 28.2 Perform Two-Way Audio 28.3 Broadcast to Connected Devices 28.4 Control Alarm Output 28.5 Record Screen Chapter 29 System Settings 29.1 Set General Parameters	
 28.1 Play Video via VSPlayer	
28.1 Play Video via VSPlayer	
28.1 Play Video via VSPlayer	

29.3 Set Linkage Action Parameters	314
29.4 Set Alarm Sound	315
29.5 Customize Icons on Alarm Center	315
29.6 Set Health Status Parameters	317
29.7 Set Screen Position	317
29.8 Enable Printing Parking Free Receipts	317
29.9 Switch Home Page Mode	318
29.10 Set Ringtone for Calling	318

Chapter 1 About Control Client

As one of the key components of the system, the Control Client provides multiple operating functionalities, including real-time live view, PTZ control, video playback and downloading, alarm receiving, log search, and so on.

This user manual describes the function, configuration, and operation steps of the Control Client. To ensure the proper usage and stability of the client, refer to the contents below and read the manual carefully before operation.

IINote

The functions on the Control Client vary with the License you purchased. For detailed information, contact our technical support.

Chapter 2 Login

Log in to the system via the Control Client for operations.

2.1 First Time Login

When normal user (except admin user) logs into the system for the first time, he/she should change the initial password and set a new password for login.

Before You Start

When you log into the system for the first time, you are required to create a password for the system pre-defined administrator user (named admin) on the Web Client before you can properly configure and operate the system.

Perform the following steps when you access the system via the Control Client for the first time as a normal user (except admin).

Steps

1. Double-click on the desktop to run the Control Client.

	Server Address	Welcome
2	Server Address 🗸 🗸	🔔 User Name 🗸 🗸
	80	A Password
E.	6	Remember Password Enable Auto-login
	111	Log In
10	100	Hide Server Address Show QR Code

Figure 2-1 Login Page

2. Enter the server parameters.

IINote

You can click **Hide Server Address** or **Show Server Address** to hide or show the server network information.

Server Address

Enter the address (IP address or domain name) of the server that running the SYS service you want to connect to.

Port

Enter the port No. of the server where the SYS service is running. The default port No. is 80. **3.** Enter the user name and password of the HikCentral Professional.

IINote

- Contact the administrator for the user name and initial password.
- For domain user account, you can check **Auto-Launch** so that you will not need to manually start the Control Client next time you start your computer.

4. Click Log In.

- 5. Click **Close** in the pop-up dialog to continue.
- 6. Set a new password and confirm the password.

A Caution

The password strength of the device can be checked by the system. We highly recommend you change the password of your own choosing (using a minimum of 8 characters, including at least three kinds of following categories: upper case letters, lower case letters, numbers, and special characters) in order to increase the security of your product. And we recommend you reset your password regularly, especially in the high security system, resetting the password monthly or weekly can better protect your product.

Proper configuration of all passwords and other security settings is the responsibility of the installer and/or end-user.

7. Click Log In to change the password.

You enter the Control Client home page after you change the password.

2.2 Normal Login (Not First Time)

Normally, you can log into the platform with the user name and password of HikCentral Professional as a normal user.

Steps

1. Double-click 🮯 on the desktop to run the Control Client.

	Server Address		Welcome	
15	10	~	1 a 💷	Ý
			£ •1	40
-			 Remember Passwor Enable Auto-login 	d
			Log In	
19			Hide Server Address Show QR Code	

Figure 2-2 Login Page

2. Enter the server parameters.

INote

You can click **Hide Server Address** or **Show Server Address** to hide or show the server network information.

Server Address

Enter the address (IP address or domain name) of the server that running the SYS service that you want to connect to.

Port

Enter the port No. of the server where the SYS service is running. The default port No. is 80.

- 3. Enter the user name and password of the HikCentral Professional.
- 4. Optional: Check Remember Password checkbox to keep the password.
- **5. Optional:** Check **Enable Auto-login** checkbox to log in to the software automatically for the next login.

INote

For domain user account, you can check **Auto-Launch** so that you will not need to manually start the Control Client next time you start your computer.

6. Click Log In.

Note

- If an failed password attempt of current user is detected, you are required to enter the verification code before you can log in. The failed password attempt from current client, other client and other address will all require the verification code.
- The failed password attempt from current client, other client (e.g., Control Client) and other address will all be accumulated. Your IP address will be locked for a specified period of time after specific number of failed password or verification code attempts. For detailed settings of failed login attempts and locking duration, refer to the User Manual of HikCentral Professional Web Client.
- The account will be frozen for 30 minutes after 5 failed password attempts. The failed password attempt from current client, other client (e.g., Control Client) and other address will all be accumulated.
- The password strength can be checked by the system and should meet the system requirements. If password strength is lower than the required minimum strength, you will be asked to change your password. For detailed settings of minimum password strength, refer to the User Manual of HikCentral Professional Web Client.
- If your password has expired, you should change the password when logging in. For detailed settings of maximum password age, refer to the User Manual of HikCentral Professional Web Client.

Enter the Control Client home page.

2.3 Change Password for Reset User and Login

If the normal user's password is reset to the initial password by the administrator, he/she should change the initial password and set a new password when logging in again.

Steps

1. Double-click 🮯 on the desktop to run the Control Client.

	Server Address		Welcome
3	Server Address	v	🚊 User Name 👻
	80		A Password
E			Remember Password Enable Auto-login
			Log In
10	10.3		Hide Server Address Show QR Code

Figure 2-3 Login Page

2. Enter the server parameters.

Server Address

Enter the address (IP address or domain name) of the server that runs the SYS you want to connect to.

Port

Enter the port No. of the server where the SYS is running. The default port No. is 80.

IINote

You can click **Hide Server Address** or **Show Server Address** to hide or show the server network information.

3. Enter the user name and password of the HikCentral Professional.

INote

- Contact the administrator for the user name and initial password.
- For domain user account, you can check **Auto-Launch** so that you will not need to manually start the Control Client next time you start your computer.

4. Click Log In.

- 5. Click Close in the pop-up dialog to continue.
- 6. Set a new password and confirm the password.

ACaution

The password strength of the device can be checked by the system. We highly recommend you change the password of your own choosing (using a minimum of 8 characters, including at least three kinds of following categories: upper case letters, lower case letters, numbers, and special characters) in order to increase the security of your product. And we recommend you reset your password regularly, especially in the high security system, resetting the password monthly or weekly can better protect your product.

Proper configuration of all passwords and other security settings is the responsibility of the installer and/or end-user.

7. Click Log In to change the password.

You enter the Control Client home page after you change the password.

Chapter 3 Home Page Overview

The default Home page shows a control panel which provides an overview of navigation about the function modules in a visible way, i.e., Alarm Monitoring, Health Status, and Map, for quick and convenient access.

IINote

- You can customize the control panel in the default Home page mode and adjust the module arrangement as you desired. For details, refer to *Customize Control Panel*.
- The default mode of the Home page is Visualization Mode. For the first time login, a prompt will appear at the top of the Home page, you can click **Switch** to switch the mode to Menu Mode. If you want to restore to the default mode, you can go to the System page and set. For details, refer to <u>Switch Home Page Mode</u>.

HikCentral Professional Control Client is composed of the following function modules by default.

Section	Module	Description
Surveillance	Monitoring	The Monitoring module provides live view, playback, smart wall (graphic card), view management, favorites management, and map management, and supports some basic operations, such as PTZ control, picture capturing, adding web page window, etc.
		For more details, refer to <u>Manage View</u> , <u>Live View</u> , <u>Playback</u> , <u>Map Management</u> , <u>Manage Smart Wall</u> (<u>Graphic Card)</u> , <u>Manage Favorites</u> , <u>Add Web Page to</u> <u>Display Window</u> , and so on.
	Parking Lot	The Parking Lot module provides entry and exit control for the detected vehicles. The system will automatically open the barrier according to the settings on the Web Client. If the barrier is not open, you can also open the barrier by pressing a button manually to allow the vehicle to pass.
		For more details, refer to <u>Entrance & Exit Control</u> .
	Intelligent Monitoring	The Intelligent Monitoring module provides the display of today's event statistics, real-time captured pictures (of faces, human bodies, and vehicles), and real-time events triggered by vehicles and persons. You can customize the contents to be displayed in this module.

Table 3-1 Function Modules of Control Client

Section	Module	Description
		For more details, refer to <u>Customize Intelligent</u> <u>Monitoring Contents</u> .
	Alarm Center	The Alarm Center module provides the display and management of alarm/event information received by the Control Client.
		For more details, refer to <u>Check Alarm and Event</u> .
	Driving Monitoring	The Driving Monitoring module provides the monitoring of vehicle driving progress and the vehicle route recording.
		For more details, refer to Driving Monitoring
Investigation	Event & Alarm Search	The Event & Alarm Search module provides the function of searching for event and alarm logs.
		For more details, refer to <u>Search Event and Alarm Logs</u> .
	Video Search	The Video Search module provides the function of searching for video footage, video on device, or VCA event related video.
		For more details, refer to <u>Video Search</u> .
	Face Search	The Face Search module provides searching for captured/ matched/frequently appeared person's/rarely appeared person's face pictures and related videos.
		For more details, refer to <u>Face Search</u> .
	Human Body Search	The Human Body Search module provides searching for captured human body pictures and related videos. For more details, refer to <u>Human Body Search</u> .
	Identity Search	The Identity Search module provides searching for the related archives of a face picture to check the captured pictures or videos of similar persons in the library, and supports picture-to-picture and picture-to-group comparison for verifying the person's identity by face similarity.
		For more details, refer to <u>Archive Search</u> and <u>Identity</u> <u>Verification</u> .
	Access Control Retrieval	The Access Control Retrieval module provides searching for access records and entry & exit counting.

Section	Module	Description
		For more details, refer to <u>Search Access Records</u> and Perform Entry & Exit Counting .
	Vehicle Search	The Vehicle Search module provides searching for related vehicle passing information. For more details, refer to <u>Search for Vehicle Passing</u>
		<u>Records</u> .
	Live Broadcast and Recording	The Live Broadcast and Recording module provides searching for live broadcast records.
		For more details, refer to <u>Search for Live Broadcast</u> <u>Records</u> .
	Driving Record Search	The Driving Record Search module provides the search of vehicle routes and driving events.
		For more details, refer to <u>Mobile Monitoring Record</u> .
Intelligent Analysis	Intelligent Analysis Overview	The Intelligent Analysis Overview module provides customizing and viewing reports.
		For more details, refer to Customize Report Dashboard .
	People Analysis	The People Analysis module provides reports for people counting, queue analysis, heat analysis, pathway analysis, and person feature analysis.
		For more details, refer to <u>Generate People Counting</u> <u>Report</u> , <u>Generate Queue Analysis Report</u> , <u>Generate</u> <u>Heat Analysis Report</u> , <u>Generate Pathway Analysis</u> <u>Report</u> , and <u>Generate Person Feature Analysis Report</u> .
	Temperature Analysis	The Temperature Analysis module provides the report for temperature analysis.
		For more details, refer to <u>Generate Temperature Analysis</u> <u>Report</u> .
	Vehicle Analysis	The Vehicle Analysis module provides the report for the number of passing vehicles.
		For more details, refer to <u>Generate Vehicle Analysis</u> <u>Report</u> .
Maintenance	Health Monitoring	The Health Monitoring module provides real-time overview and history overview of the resources and service status.

Section	Module	Description
		For more details, refer to <u>Real-Time Health Status</u> Overview and <u>Historical Health Data Overview</u> .
	Resource Status	The Resource Status module provides the status of the resources.
		For more details, refer to <u>Resource Status</u> .
	System Log	The System Log module provides searching, viewing, and backing up the log files.
		For more details, refer to <u>Log Search</u> .
Evidence Management	Evidence	The Evidence module provides the management of evidences and files that are not linked with evidences.
Center		For more details, refer to <u>Add Evidence</u> and <u>Manage</u> <u>Unlinked Files</u> .
	Operation Record	The Operation Record module provides the management and search of evidence upload or download records.
		For more details, refer to Manage Operation Records
Tool	Smart Wall	The Smart Wall module provides the function of displaying the decoded video on smart wall.
		For more details, refer to <u>Manage Smart Wall (Decoding</u> <u>Device)</u>
	Arming Control	The Arming Control module provides arming and disarming of the resources managed in the system.
		For more details, refer to <u>Perform Arming Control for</u> <u>Alarms</u> .
	Video Intercom	The Video Intercom module provides voice talk with residents by calling their indoor stations.
		For more details, refer to <u>Video Intercom</u> .
	VSPlayer	In the VSPlayer module, you can run the software and play video files stored in the local PC.
		For more details, refer to <u>Play Video via VSPlayer</u> .
	Two-Way Audio	The Two-Way Audio module provides the function of voice talk between the Control Client and devices, and supports getting and playing the real-time audio on the Control Client.
		For more details, refer to <u>Perform Two-Way Audio</u> .

Section	Module	Description
	Broadcasting	The Broadcasting module provides the function of distributing the audio content to the added device if the device has an audio output.
		For more details, refer to <u>Broadcast to Connected Devices</u>
	Alarm Output Control	The Alarm Output Control module provides the function of controlling the alarm output remotely by the Control Client.
		For more details, refer to <u>Control Alarm Output</u> .
	Record	The Record tool is used to record operations on the screens. The recorded video files can be saved as the evidence.
		For more details, refer to <u>Record Screen</u> .
Management	System	The System module provides basic settings and application settings.
		For more details, refer to <u>System Settings</u> .
	Help	The Help module provides help information, such as user manual, license details, and software version of the Control Client.
	Download Center	The Download Center module supports viewing and managing the downloading tasks.
		For more details, refer to <u>Manage Downloading Tasks</u> .
	Local Picture	The Local Picture module provides the search and management of local pictures.
	Local Recording	The Local Recording module provides the search and management of local video files.

3.1 Customize Control Panel

You can select modules to display on the control panel and customize the module arrangement.

Steps

- **1.** In the top left corner of the control panel, click **My Control Panel** to unfold the drop-down list.
- 2. Click Add Control Panel in the drop-down list to start customizing a control panel.

My Control Facel	You can add/moverthilds the windows.	Restor Delaity See
Surveillance		
C) Greek		
🔟 Door and Deatter		
5 week		
Real Time People Counting		
A face factory-from		
(E) has Comparison		
🛱 Arm Montoing		
ш ч		
(2) Institution		
🛱 Welter		
Intelligent Analysis		
1 Annotation		

Figure 3-1 Customize Control Panel

- **3.** In the top left corner of the control panel adding page, enter a name for the control panel.
- 4. On the right panel, select a window.
- 5. On the left panel, click a module name to show the module configuration panel on the left.
- 6. Select and drag/double click a camera/map/web page, or set module parameters and click Save.

iNote

- When adding the Camera or Map module, you can edit the added modules. But when adding other modules (except the Camera and Map modules), you cannot edit the added modules.
- When adding the Health Monitoring module, setting module parameters is not required. After clicking the module name, the module will be directly added and displayed in the selected window.
- When adding the Web Page module, you can enter the URL or IP address of the web page in the input field in the top right corner of the window and press Enter on the keyboard to go to the web page.

The module is added to the selected window and displayed in a visualized way. **7. Optional:** Perform the following operation(s).

Edit Module Parameters	Click 🜌 in the top right corner of the window to edit the module parameters.
Remove Module	Click 💼 in the top right corner of the window to remove the module from the window.

Customize ModuleDrag the module to the desired window to customize the moduleArrangementarrangement on the control panel.

- **8. Optional:** In the top right corner of the control panel adding page, click **Cancel** to cancel customizing the control panel.
- **9. Optional:** In the top right corner of the control panel adding page, click **Restore Default** to restore to the default control panel.
- **10.** In the top right corner of the control panel adding page, click **Save** to save the custom control panel.
- **11. Optional:** Perform the following operation(s).

Edit Control Panel	In the top right corner of the Control Client, click Edit Control Panel to edit the control panel.
Switch to Full Screen	In the top right corner of the Control Client, click Full Screen to display the control panel in full screen mode.
Open Auxiliary Screen	In the top right corner of the Control Client, click 📓 to display the control panel on the auxiliary screen.

3.2 Customize Navigation Bar

To conveniently access some frequently used or important modules, you can customize the navigation bar.

Steps

In the top left corner of the Client, select All Modules to display the navigation bar and the All Modules pane.

Cartral Panel	All Modules					
Al Multim						
Secollars	Surveillance				lower Well	
	C3 Messary	1 1	f recolu	C intelligent Marchinering	Arrived Control	
Parking type	D Ann Center	6. E	3 - Trany Manager	A nece	Webper Statements	
				- 	Viller	
investigation	Investigation					
	The Barris America	6 3	Viles Section	A feathern d	front sting	
	the second second	B	E meny been	Anna Constant (2)	Alarm Chippel Control Report	
	E venesteen	đ	. Los Brooked and	Diring Record Search	Vanagement	
instigent Analysis	Intelligent Analysis					
	E Indigent Analysis -		§ People Rougels ()	1 Terrentine And 1	nen. Denskalderer	
	ES. Vende Avenue				ing Trans	
	Maintenance				Local Recording	
	2 Feat Automa		a management	St Autor (G		
Maintenance	·2·			60 . CHILLINE (1986)		
I South Manharing	Evidence Management Ca	ali ali				
	💁 traens		Eleverating Record			
Establishe Management Center						
Teel						

Figure 3-2 Navigation Bar and All Modules Panel

- **2.** On the All Modules panel, drag the modules to the desired area to customize the module arrangement.
- **3.** On the All Modules panel, move the cursor to a module item.

An icon 📷 appears beside the module name.

- Click at to add the selected module to the navigation bar.
 The icon at the corresponding module turns to at .
- 5. Optional: Click 📷 to remove the module from the navigation bar.

Chapter 4 Manage View

A view is a window division with resource channels (e.g., cameras and access points) linked to each window. View mode enables you to save the window division and the correspondence between cameras and windows (or correspondence between map and window) as the default so that you can quickly access these channels and/or map later. For example, you can link camera 1, camera 2, and camera 3 located in your office to the certain display windows and save them as a view called *office*. Then, you can access the view *office* and these cameras will display in the linked window quickly.

Perform this task when you need to get quick access to a certain set of channels for live view or playback.

IINote

- For live view, the view mode can save resource type, resource ID, stream type, position, and scale after digital zoom, preset No., and fisheye dewarping status.
- For playback, the view mode can save resource type, resource ID, position, and scale after digital zoom, and fisheye dewarping status.

Steps

- 1. Click Monitoring on My Dashboard to enter Monitoring page.
- 2. Click 📰 to enter the View page.
- 3. Optional: Add a custom view group.
 - 1) Select Public View or Private View to add the view group.

INote

The view groups and views that belong to the private view group are hidden from the other users.

2) Click 🕫 .

- 3) Create a name for the group or use the default name.
- 4) Click **OK** to add this view group.

4. Add a view.

- 1) Select a view group.
- 2) Click + .
- 3) Create a name for the view or use the default name.
- 4) Click Add to select cameras.
- 5) Select a stream type for each camera in the Stream Type column, or you can click **Set Stream Type** to select a stream type.
- 6) Select a preset you want to switch to for each camera.
- 7) Optional: Click Up or Down to adjust the camera order.
- 8) Optional: Select camera(s) and click Delete to delete them.
- 9) Select a layout for the view.

- 10) Select a switching interval or click **Custom Time Interval** to set the switching interval among the selected cameras.
- 11) Click **Add** to add this view.
- **5. Optional:** You can also Drag the channels to the window or double-click the channels to start live view or playback. Save the view with the displayed view division and channels.
 - Click → Save View to save the current window division mode and displayed channels and (or) map as the selected view.
 - Click Save as View to save the current window division mode and displayed channels and (or) map as a new view by creating view name (optional) and selecting the view saving path.

Ĵ∎Note

If the added view is not selected before, you can also save the current window division and displayed channels as a new view.

6. Optional: Perform the following operations after adding the view.

Edit View	Click 🜌 to edit the view settings, such as the view name and camera's stream type.
Add Camera/Map to the Existing View	 a. Go to Monitoring. b. Select camera(s) or map. ✓✓✓✓ Note You can press Ctrl on the keyboard to select multiple cameras. c. Click S → Save View to save the camera(s) or map to an existing view.
Delete Camera/Map from View	 a. Move the cursor to a camera or a map in a view. b. Click a to close the current camera or map window. c. Click a → Save View to save the current view.
Live View/ Playback in View Mode	Select a view, and click □□ → Play to start live view or playback in view mode. See <u>Start Live View in View Mode</u> and <u>Start Playback in View</u> <u>Mode</u> for details.
Delete View or View Group	Click m to delete the custom view or view group.
Reset View	Click 🕤 to restore the view to its initial settings.
Search View	Click 💽 , and enter keywords in the search box to search for target view(s).

Chapter 5 Live View

You can view live video of the connected cameras using Live View. During live view, you can control PTZ cameras, record video clips, capture images, view instant playback, add cameras to Favorites, etc. For the ANPR camera, you can view the recognized license plate number. For the face recognition device, you can view the face comparison information of the detected faces. For the access points that are related to cameras, you can control the access point status in real-time and check the card swiping records. Also, you can enter smart wall (graphic card) mode and display the resources on the smart wall.

Navigation Panel

\oplus	Monitoring	Show live-view-available resources that are grouped in areas in each site.
$\langle \! \! \mathfrak{S} \! \! \rangle$	Real-Time People Counting	View real-time people counting status of each people counting group.
☆	Favorites	View Favorites created by you and Favorites shared by others. You can quickly access the cameras that are added in Favorites.
83	View	Create custom view groups and views of available channels. Edit existing view groups and views.
4	Face Comparison	View the face comparison information between the detected faces and the face pictures in a face comparison group.
	Smart Wall	Enter Smart Wall (Graphic Card) Mode. Set window division and adjust display window on smart wall. Note For more details, refer to <u>Display Contents on Smart Wall</u> <u>in Smart Wall Mode</u> .
2	PTZ Control	Control a PTZ camera. Create presets for PTZ cameras. Create patrols for PTZ cameras.

		Create patterns for PTZ cameras.
Ø	Add Web Page Window	Add web page(s) to the Live View or Playback window. Note For details, refer to <u>Add Web Page to Display Window</u> .

5.1 Start Live View in Area Mode

You can start the live view of cameras grouped in an area.

Before You Start

Make sure you have grouped cameras into areas via the Web Client. For details, refer to the User Manual of HikCentral Professional Web Client.

Steps

1. In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Monitoring .

The areas which the current user has permission to access are listed and the resources which the user has permission to access are shown in the corresponding areas.

JiNote

For setting the user permission, refer to User Manual of HikCentral Professional Web Client.

2. Optional: Click 📰 in the upper-right corner to change live view window division.

Average

All the divided windows are distributed in average.

Highlighted

The highlighted window is used to display the live video of the critical camera.

Horizontal

The divided windows are distributed horizontally in the window.

Vertical

The divided windows are distributed vertically in the window.

Others

Other types of window division besides the types above.

Start live view.

For One Camera	Drag a camera to the display window to start the live view of the camera, or double-click the camera to start the live view in a free display window.
For All Cameras in The Same Area	Drag an area to a display window, and click Play in Batch , or double-click the area to start the live view of all camera in the area.

-	Note

The display windows automatically adapt to the number of cameras in the area.

4. Optional: Perform further operations after starting live view.

Operations on Live View Toolbar	Move the mouse cursor to the lower edge of the live view window and perform more operations.
	i Note
	For details about the functions of different icons, refer to <u>Customize</u> <u>Icons on Live View Window</u> .
View Alarm Information and Acknowledge Alarm	When an alarm is triggered on a resource, the title bar of the resource's live view window will turn red. Click the red title bar to view the alarm information and acknowledge the alarm.
Stop Live View	Click 📓 that appears in the upper-right corner when the mouse pointer is over the display window. You can also click 🔜 above the display window to stop the live view of all the display windows.

5.2 Start Live View in View Mode

You can quickly start the live view of the cameras managed in a view.

Before You Start

Make sure you have added at least a view. Refer to Manage View for details.

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow All Modules \rightarrow Surveillance \rightarrow Monitoring$.
- 2. Select View on the left.
- 3. Start the live view of the cameras related to the view.
 - Double click a view.
 - Move the mouse cursor to a view, and click **■** → **Play** beside the view name.

INote

You can switch the added views from the drop-down list above the live view window.

4. Optional: Perform further operations after starting live view.

Operations onMove the mouse cursor to the lower edge of the live view window and**Live View Toolbar**perform more operations.

	I II Note For details about the functions of different icons, refer to <u>Customize</u> <u>Icons on Live View Window</u> .
View Alarm Information	When an alarm is triggered on a resource, the title bar of the resource's live view window will turn red. Click the red title bar to view the alarm information and acknowledge alarm.
Adjust Windows'	Drag the windows to adjust the sequences.
Sequence	i Note
	The changed sequence will be restored after restarting live view in view mode.
Stop Live View	Click 📓 that appears in the upper-right corner when the mouse pointer is over the display window. You can also click 💽 above the display window to stop the live view of all the display windows.

5.3 Auto-Switch Cameras in an Area

You can play the live view of all cameras in an area in turn in one window and perform further operations after auto-switch starts.

Steps

1. In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Monitoring .

The areas which the current user has permission to access are listed and cameras which the user has permission to access are shown in each area.

```
IINote
```

For setting the user permission, refer to User Manual of HikCentral Professional Web Client.

- 2. Start auto-switch in the area.
 - Drag an area to the live view window and select **Single-Screen Auto-Switch** to start the autoswitch the cameras of the area in the selected display window.
 - Click •••• on the right side of the area name and click **Area Auto-Switch** to switch the cameras of the area in the live view window.
- **3. Optional:** Move the cursor to the live view window and perform further operations after autoswitch starts.

Adjust Switching Interval	Click M or M in the lower-left corner of the live view window to adjust the interval of the auto-switch.
View Previous or Next Camera	Click 🔣 or 📓 in the lower-left corner of the live view window to go to the previous or next camera.

Pause

Click **IIII** in the lower-left corner of the live view window to pause the auto-switch.

4. Optional: Move the cursor to the display window to access the icons for further operations.

i Note

For details about these icons, refer to *Customize Icons on Live View Window*.

5.4 PTZ Control

The Control Client provides PTZ control for cameras with pan/tilt/zoom functionality. You can set the preset, patrol and pattern for the cameras on the PTZ control panel.

INote

The PTZ control function should be supported by the camera.



Figure 5-1 PTZ Control Panel

The following buttons are available on the PTZ control panel:

ð	Lock the PTZ for a designated time period. When the PTZ is locked, users with lower PTZ control permission levels cannot change the PTZ controls.
	Note
	For details about setting the PTZ control permission level, refer to the User Manual of HikCentral Professional Web Client.
	Cancel the PTZ lock.

۲	Direction Button, Auto-scan and PTZ speed.
ದೆ / ಡ	Zoom in or out the video for cameras that do not have their own optical zoom capabilities. Click again to disable the function.
0/@	Used for adjusting the luminance of the image. The larger the iris is, the more the light enters, and the brighter the image will be.
0/7	Click Focus + move the focal point forward, and click Focus - to move the focal point backward.

In the live video display window, you can also click the icon state to enable window PTZ control. Move the cursor to the direction you desired and click on the image to pan or tilt. You can also click and drag the cursor with a white arrows to the direction you desired for a quick direction control.

5.4.1 Configure Preset

A preset is a predefined image position which contains configuration parameters for pan, tilt, zoom, focus and other parameters. You can also set a virtual preset after enabling digital zoom.

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Monitoring .
- **2.** Start live view of the PTZ camera.
- 3. Click 💽 to enter the PTZ Control mode.
- **4.** Click **W** to enter the PTZ preset configuration panel.
- 5. Use the direction buttons and other buttons to control the PTZ movement.
- 6. Select a PTZ preset number from the preset list and click 🗾 .
- 7. Create a name for the preset in the pop-up window.
- 8. Click OK to save the settings.

IINote

- Up to 256 presets can be added.
- The unconfigured preset is gray.
- The configured preset is highlighted.
- 9. Optional: After adding the preset, you can do one or more of the followings:

Call Preset Double-click the preset, or select the preset and click <a>[.

Edit Preset Select the preset from the list and click 🜌 .

Delete Preset Select the preset from the list and click

5.4.2 Configure Patrol

A patrol is a scanning track specified by a group of user-defined presets (including virtual presets), with the scanning speed between two presets and the dwell time of the preset separately programmable.

Before You Start

Two or more presets for one PTZ camera need to be added. Refer to *Configure Preset* for details about adding a preset.

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Monitoring .
- 2. Start live view of the PTZ camera.
- **3.** Click **m** to enter the PTZ Control mode.
- 4. Click 🕎 to enter the PTZ patrol configuration panel.
- **5.** Add presets to the patrol.
 - 1) Click Z on the right side of a patrol.
 - 2) Select **Device Preset** or **Virtual Preset** as the preset type.
 - 3) Click 📰 to add a configured preset, and set the dwell time and patrol speed.

INote

- The preset dwell time ranges from 15 to 30s.
- The patrol speed ranges from 1 to 40.
- The unconfigured patrol is gray.
- The configured patrol is highlighted.
- 4) Repeat the above steps to add other presets to the patrol.

iNote

By default, the first preset is added to the patrol list. Double-click the preset, speed, and dwell time to access a drop-down configuration list.

ed Time

Figure 5-2 Configure Patrol

6. Optional: Perform the following operations after you add the preset.

Edit Added Preset	Double-click the corresponding field of the preset to edit the settings.
Remove Preset from Patrol	Click 🔤 to remove the preset from the patrol.
Adjust Preset Sequence	Click 📷 or 🔜 to adjust the presets sequence.

7. Click OK to save the patrol settings.

iNote

Up to 8 patrols can be configured.

8. Optional: After setting the patrol, you can do one or more of the followings:

Call Patrol Click **to start the patrol**.

i Note

When the patrol is working, it will stop if you start performing PTZ control including direction button control, zoom in/out, focus +/-, iris +/-, etc. The patrol will continue working after you have stopped PTZ control for 15 seconds.

Stop CallingClick Image to stop the patrol.Patrol

5.4.3 Configure Pattern

Patterns can be set to record the movement of the PTZ.

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Monitoring .
- 2. Start live view of the PTZ camera.
- 3. Click 📰 to enter the PTZ Control mode.
- **4.** Click **m** to enter the PTZ pattern configuration panel.
- 5. Click 🔤 to start recording the movement path of the pattern.
- 6. Use the direction buttons and other buttons to control the PTZ movement.
- **7.** Click **1** to stop and save the pattern recording.

iNote

Only one pattern can be configured, and the newly-defined pattern will overwrite the previous one.

8. Optional: After setting the pattern, you can do one or more of the followings:

Call Pattern Click I to call the pattern.

iNote

When the pattern is working, it will stop if you perform PTZ control including direction button control, zoom in/out, focus +/-, iris +/-, etc. The pattern will continue working after you have stopped PTZ control for 15 seconds.

Stop CallingClick image to stop calling the pattern.PatternClick image to clear the recorded pattern.

5.5 Manual Recording and Capture

You can record video files and capture pictures manually during live view.

Manual Recording

Record the live video during live view if needed and store the video files in the local PC.

Capture

Capture pictures during live view if needed and store the pictures in the local PC.

5.5.1 Manual Recording

During live view, you can record the live video manually and you can export the video as video evidence.

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Monitoring .
- 2. Move the cursor to the live view display window to show the toolbar.
- 3. Click 🔯 in the toolbar of the display window to start the manual recording. The icon turns to 📷 .

IINote

During the manual recording, **Recording...** will display in the upper-right corner of the display window.

4. Click i to stop recording.

A dialog directing to the saving location of the file pops up.

IINote

- You can change the saving path of video files in System. For details, see <u>Set General</u> <u>Parameters</u>.
- The video cannot be saved if the free space on your disk is less than 2 GB.
- 5. Optional: Perform further operations in the pop-up dialog box after manually recording.

Open Folder Click **Open Folder** to access the video file folder.

Save As	Click Save As and specify file saving path to change the saving location for the recorded video files.
Save as Evidence	Click Save As and check Save as Evidence , and then edit the information to save the video footage as evidence.
	Note
	See <u>Save Found Video Footage as Evidence</u> for details.

5.5.2 View Manually Recorded Videos

The manually recorded files during live view are stored on the PC on which the Control Client is running. You can search and check the video files in Local Recoding.

Follow the steps to view the recorded videos.

Steps

- In the top left corner of Control Client, select All Modules → Management → Local Recording .
- 2. In the **Camera** field, click 🗈 to select the camera(s) that you want to search video recordings in the area list.
- **3.** In the **Time** field, set the time range for this search.
- 4. Click Search.

Video files recorded between the start time and end time are shown on the right.



Figure 5-3 Local Recording

5. To play a video file using the VSPlayer, click Son the video file.

IINote

For detailed instructions about VSPlayer, click and select **User Manual** to see the User Manual of VSPlayer.

6. Optional: Select video files and perform further operations on the files.

Save Video File to Local PC	Click Save As and then specify a local path to save the selected video file(s).
Delete Video File	Click Delete to delete the selected video file(s).
Save Video File as Evidence	 a. Click Save As to open the Export panel. b. Check Save as Evidence and then edit the information to save the video file as evidence.
	i Note
	For details, see <u>Save Found Video Footage as Evidence</u> for details.

5.5.3 Capture Pictures

During live view, you can take a quick snapshot of the live video via the Control Client.

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Monitoring .
- 2. Move the cursor to the live view display window to show the toolbar.
- 3. Click 📷 in the toolbar to capture a picture.

A dialog box directing to the saving location pops up.

IINote

- You can change the saving path for captured pictures in System. For details, see <u>Set General</u> <u>Parameters</u>.
- The picture cannot be saved if the free space on your disk is less than 512 MB.

4. Optional: After the dialog box popped up, perform the following operation(s).

CheckClick Open Folder in the dialog box to open the folder where the captured picturesPicturestored to and view pictures.

Edit a. Click Edit in the dialog box to open the Capture window.

Picture





Figure 5-4 Capture Window

- b. Press and move the cursor on the picture to draw. For example, you can mark the suspicious persons in the picture.
- c. Click **Save As** and specify the path to save the edited picture.



5.5.4 View Captured Pictures

The captured pictures in live view are stored on the PC on which the Control Client is running. You can search and check the picture files in Local Picture.

Follow the steps to view the captured pictures.

Steps

- In the top left corner of Control Client, select → All Modules → Management → Local
 Picture .
- 2. In the Camera field, click 🗈 to select the camera(s) that you want to search captured pictures in the area list.
- 3. In the Time field, set the time range for this search.
- 4. Click Search.

Pictures captured between the start time and end time are shown on the right.

Local Picture			
	A		

Figure 5-5 Local Picture

- 5. Optional: Double-click a picture for a larger view.
- **6. Optional:** Select picture(s) and perform further operations.

Print Pictures	Click Print to print the selected pictures.
Save Picture to Local PC	Click Save As and then specify a local path to save the selected picture(s).
Delete Picture	Click Delete to delete the selected picture(s).

5.6 View Dewarped Live View of Fisheye Camera

You can set center calibration and view dewarped live view of a fisheye camera in the client. Dewarping refers to the process of perspective correction of an image, to reverse the effects of geometric distortion caused by the fisheye camera lens. It allows the user to cover a wide area with a single device and have a "normal" view of an otherwise distorted or reversed image. Also, during live view, you can perform more operations such as adjusting view angle and zooming in/out view.

Steps

1. Start live view of a fisheye camera.

IINote

For details, refer to **<u>Start Live View in Area Mode</u>** and <u>**Start Live View in View Mode**</u> .

2. Optional: Set center calibration of the fisheye camera to calibrate the center of fisheye image.
 1) On the toolbar of display window, click
 →
 to open center calibration window.




Figure 5-6 Center Calibration Window

2) Move or adjust the size of the rectangle in red dashed line on the video to calibrate the center of camera view as desired.

iNote

Center calibration should be operated within proper scope, otherwise it will fail.

- 3) Click Save.
- **3.** On the toolbar of display window, click **i** to enter the fisheye dewarping mode and view live view.



Figure 5-7 Fisheye Dewarping

4. Optional: Perform the following operations as desired.

Adjust View Angle	Put the cursor on the live video, and drag the video to adjust the view angle.
Zoom in/out View	Put the cursor on the live video, and scroll the mouse wheel to zoom in or out the view.
Perform PTZ control	Use the PTZ panel on the left side to perform PTZ control of the camera.
	Note
	Setting pattern is not supported by fisheye cameras.

5.7 View People Density in Live View

For a camera linked to a behavior analysis server, you can view its live video, heat map that shows people density data, and real-time statistics of people amount simultaneously. In this way, you can

monitor people density in the field of view of the camera in real time, thus prevent excessive people gathering in special occasions such as epidemic outbreak.

Before You Start

- Make sure you have purchased the license that supports people density analysis.
- Make sure that you have added a behavior analysis server to the SYS and linked cameras to the server, and that you have set people density analysis tasks for the cameras on the Web Client. For details, see *HikCentral Professional Web Client User Manual*.
- Make sure you have configured people density analysis on the behavior analysis server. For details, see the user manual of the server.

Steps

INote

The function should be supported by the camera.

1. Start live view of a camera linked to the behavior analysis server.

IINote

For details, refer to **Start Live View in Area Mode** and **Start Live View in View Mode** .

2. Hover the cursor onto the live view image to show the toolbar, and then click on the toolbar to enter the people density analysis mode.

The display window will be divided into three parts: the live video (optical view) of the camera, a heat map, and a line chart.

On the heat map, the persons on the image are highlighted, which allows you to view their motion clearly.

On the line chart, the variation trend of the people amount and the real-time people amount are displayed.

Live View	N the view -X Heat Map
5	Une Chart

Figure 5-8 View People Density in Live View

3. Optional: Perform the following operations if required.

Capture and Manual Recording	Click 📷 to capture a picture.
Print Captured Picture	Click 🚭 to capture a picture and then print it.
View Camera Status	Click 🔝 to view the camera's status information, including frame rate, resolution, bit-rate, network status, signal status, recording status, video storage location, picture storage location, etc.

5.8 Perform Manual Panorama Tracking

During live view, you can enable the panorama tracking manually to locate or track the target appeared in the view of bullet or box camera with a linked speed dome. You can also check and test the calibration results about panorama tracking settings for auto-tracking.

Before You Start

Make sure you have configured the panorama tracking rules for the box or bullet camera on Web Client. For more details, refer to *User Manual of HikCentral Professional Web Client*.

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow All Modules \rightarrow Surveillance \rightarrow Monitoring$.
- 2. Start the live view of box/bullet camera, and linked speed dome.
- 3. Click 🔄 on toolbar of box/bullet camera to enable manual panorama tracking.

iNote

If you choose to enable manual panorama tracking, the auto panorama tracking will not take effect; if you choose not to enable manual panorama tracking and enable **Auto-Tracking** when configuring panorama tracking on the Web Client, when the configured VCA event is triggered by target, the linked speed dome will perform the automatic panorama tracking.

4. Click or draw a rectangle on the live view image of the box/bullet camera, and the speed dome will switch to the close-up view.



Figure 5-9 Manual Panorama Tracking

5.9 Create Zooming Area to View Detailed Live View

You can play the full-frame live view of a camera and zoomed-in parts side by side at the same time by creating zooming areas.

Before You Start

Make sure you have added camera(s) via the Web Client.

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow All Modules \rightarrow Surveillance \rightarrow Monitoring$.
- 2. Start the live view of a camera. See detailed instructions in *Start Live View in Area Mode* .
- **3.** Create a zooming area in the full-frame live view of the camera to view details of this area in a new display window.
 - For a normal camera, click **m** and draw a rectangle on the video.




Figure 5-10 Zooming Area Window (Normal Camera)

IINote

Up to 5 zooming areas can be added.

- For a fisheye camera, click and draw a rectangle on the video.




Figure 5-11 Dewarped Zooming Area Window (Fisheye Camera)

IINote

- Up to 8 zooming areas can be added.
- For fisheye cameras, you can view the dewardped zooming image in the new live view window.

Live view of zooming area(s) you create will play in the new live view window(s). **4. Optional:** Perform further operations after creating a zooming area.

Delete ZoomingMove the cursor to a zooming area on the main live view window, and
click is to delete the area.

Edit Zooming Area	Drag the edge of a zooming area to adjust the size of the area.
Stop Live View	On the live view window of a zooming area, click 🔀 in the upper right corner to close the live view window.
	Note
	If you want to show the live view window of the zooming area again, you need to click 📴 / 🚾 on the toolbar of the main live view window, and the area to a live view window.
Adjust Window Sequence	Drag the live view windows to adjust their sequences.

5.10 View Detected Event in Live View

The detected events, including ANPR events, face comparison events, access events, and passing vehicle records can be displayed in real-time during live view. You can view the event details, filter the events, and clear the events.

Before You Start

Make sure you have added devices and events.

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow All Modules \rightarrow Surveillance \rightarrow Monitoring$.
- 2. Start the live view. See detailed instructions in Start Live View in Area Mode .
- **3.** Click at the bottom of the client to show the event list.
- **4.** Select **All/Face Comparison/Access Control/Vehicle Record** tab to view the corresponding event information.

All Face Comparison	Access Control Vehic	e Record			
Record Type	Source	Description	Client Time	Operation	
NTP Auto Time Synchronization			09/03/09		
NTP Auto Time Synchronization			0903.08		
NTP Auto Time Synchronization			085810		
Remote: Logout			085634	10	
Remote: Remained Locked (Grede			085409		
Door Locked (Door Lock)			08.54.09		
NTP Auto Time Synchronization			085354		

Figure 5-12 Event List

Face Comparison

A face comparison event refers to any event involving a camera with face recognition capability.

Access Control

An access control event refers to any events with an access point involved. Click **Access Control** to go through access control events, and on the right pane, you can view the person details.

Vehicle Record

A vehicle record refers to any passing vehicle information captured by an ANPR camera. **5. Optional:** Perform further operations.

View Event Details	Click 🔝 to view the event details.
Add to List	 If the client recognizes a person that is not in the person list, you can add the person to the face comparison group by clicking . See details in <u>View Detected and Matched Face in Live View</u>. If the client recognizes a vehicle license plate that is not in the vehicle list, you can add it to the vehicle list by clicking . See details in <u>Add</u> <u>Recognized Vehicle to Vehicle List</u>.
Forgive Anti- Passback Violation	When a person attempts to use a card out of anti-passback rule's sequence, the access will be denied. This is called "Anti-Passback Violation". When anti-passback violation occurs, no entry is allowed unless the anti-passback violation event is forgiven.
	In the Access Control event list, you can forgive an anti-passback event by clicking 💽 in the Operation column.
Search Access Records	For visitor access events, click 📷 to go to Access Record Retrieval page to search access records of the visitor by customizing searching conditions.
Search Events	For door events, click 📷 to go to Event & Alarm Search page to search event by customizing searching conditions.
Subscribe All Face Comparison Events	In the Face Comparison event list, check Subscribe All so that the current Control Client can receive events from all the face comparison groups and display the events in the event list.
Subscribe All Vehicle Records	In the Vehicle Records list, check Subscribe All so that the current Control Client can receive all passing vehicle records from ANPR cameras and display the records in the list.
Filter Event	Click 📷 to select the resource to filter the related event.
Clear Event	Click T to clear all the detected events.

5.11 More Functions

There are more other functions supported during the live view, including batch starting wipers, opening auxiliary screen(s), etc.

Third-Party Integrated Resource

Click @ to control the third-party resource(s).

Batch Start Wipers

Click R and select cameras to start wipers of the selected cameras in a batch. Click the button again to stop their wipers in a batch.

Customize Live View and Playback Toolbar

Click $\blacksquare \rightarrow$ Video \rightarrow Toolbar to customize the icons on the Live View and Playback toolbar.

IINote

For details about the different functions of the icons, refer to <u>Customize Icons on Live View</u> <u>Window</u> and <u>Customize Icons on Playback Window</u>.

Add to Favorites

Click 😭 to add the camera to Favorites. You can click **Create Favorites** to create a new Favorites.

Open Auxiliary Screen

Live video can be displayed on different auxiliary screens to monitor multiple scenes. Click above the display window area to open an auxiliary screen. Up to 4 auxiliary screens for live view are supported.

5.12 Customize Icons on Live View Window

You can customize the icons on the toolbar of the live view window, adjust the icon order, and control whether to always show toolbar on the live view window or not.

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Management \rightarrow System .
- 2. Select Video → Toolbar .
- **3.** In **Live View Toolbar** section, add or remove the icons to show or hide the icons on the live view toolbar.
- 4. Drag the icons in the icon list to adjust the order.

4	Audio Control	Turn off/on the sound and adjust the volume.
Ø	Capture	Take a snapshot of the current video and save it to the current PC.
		Note
		After capturing a picture, a thumbnail will pop up on the upper-right corner. You can click Search by Picture to search the captured picture, archive, and identity verification related with the captured picture.
•	Print	Take a snapshot of the current video and print it.
		Note
		You can enter some descriptive information of the picture to be printed.
۲	Record	Start manual recording. The video file will be stored in local PC.
۲	Instant Playback	Switch to instant playback mode to view the recorded video files.
•	Two-Way Audio	Start two-way audio with the camera to get the real-time audio from the device to realize voice talk with the person at the device.
Q	Digital Zoom	Zoom in or out the video for cameras that do not have their own optical zoom capabilities. Click again to disable the function.
2	PTZ Control	Activate the PTZ icons on the image to pan, tilt, or zoom the image.
	Fisheye Expansion	Available for fisheye camera. In the fisheye dewarping mode, the Control Client will correct the video image and reverse the effects of geometric distortions caused by the fisheye camera lens. See <u>View Dewarped Live View of</u> <u>Fisheye Camera</u> for details.
83	Camera Status	Show the camera's recording status, signal status, connection number, etc.

•	Arming Control	Open the arming control window of the camera to arm or disarm the camera's event. The Control Client can receive the armed events or alarms.
3	Switch Stream Type	Switch the live view stream to main stream, sub-stream (if supported), or smooth stream (if supported). Note The smooth stream will show if device supports. You can switch to smooth stream when in low bandwidth
ŧ₽	Display on Smart Wall	situation to make live view more fluent. Display the live video on the smart wall. See <u>Manage</u> <u>Smart Wall (Decoding Device)</u> for details.
0	VCA Search	Display the VCA Search window. You can set VCA rule to search video files and filter the videos by VCA event types. Refer to <u>Search VCA Event Related Video</u> for details.
6	Alarm Output	Display the Alarm Output Control page and turn on/off the alarm outputs of the connected camera. See <u>Control</u> <u>Alarm Output</u> for details.
	Add Tag	Add a tag for the video footage in a selected time range during live view. See <u>More Functions</u> for details.
1	Visual Tracking	Track an individual (such as a suspect) across different areas without losing sight of the individual. See <i>User</i> <i>Manual of HikCentral Professional Web Client</i> and <u>Visual</u> <u>Tracking</u> for details.
	Create Zooming Area	Create zooming area(s) on the video image to view detailed live view. See <u>Create Zooming Area to View</u> <u>Detailed Live View</u> for details.
58,	Create Dewarped Zooming Area	Create dewardped zooming area(s) on the video image to view detailed live view. See <u>Create Zooming Area to View</u> <u>Detailed Live View</u> for details.
-	Search by Picture	Search for the target person by the captured pictures. See <i>Search Captured Face Pictures and Related Videos</i> for details.
÷	Manual Smart Linkage	Locate or track the target appeared in the view of bullet or box camera with a linked speed dome. See for details.

M	People Density Monitoring	View people density data and real-time statistics of people amount. See <u>View People Density in Live View</u> for details.
4	Broadcast	Start broadcasting to the connected speaker units.
ц.	Video Enhancement	Adjust the video image including brightness, saturation, etc.
0	Rotate Image	Rotate a image.
•	Park Action	Click the icon and the speed dome will save the current view to the preset No.32. The device starts to park at preset No. 32 automatically after a period of inactivity (park time).

iNote

The icons on the toolbar in the live view window vary with the device's capabilities.

5. Optional: Check Always Display Toolbar to always show the toolbar on the live view window.

6. Click Save.

Chapter 6 Real-Time Temperature and People Counting Monitoring

With people counting analysis function, you can monitor the people stayed in an area while monitoring their features (including skin-surface temperature, wearing mask or not, similarity with already-added persons, etc.).

On the Control Panel, click $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Monitoring \rightarrow \blacksquare People Counting Analysis .




Figure 6-1 Real-Time Temperature and People Counting Monitoring

Real-Time Temperature Screening

On the Monitoring page, after starting live view of a skin-surface screening point, you can view the latest skin-surface temperature information on the right.

Persons with different features will be marked by different colors. Green color indicates the detected person's skin-surface temperature is normal and the person is wearing a mask. Orange indicates a person with normal skin-surface temperature wears no mask. Red indicates a person with abnormal skin-surface temperature.

If there are persons whose skin-surface temperatures are abnormal, you will know at the first time. Besides, you will be able to quickly locate the persons according to the displayed screening point name. Also, you can go to the People Counting Analysis page and drag the current camera's corresponding people counting group to the live view area. In this way, you can monitor the people counting data during live view.

Real-Time People Counting

On the left, all the people counting groups are displayed. Drag one or more people counting group to the live view area to show the real-time people counting data. The real-time people counting data include people stayed and remaining entries of the monitored area, and whether more people are allowed to enter.

Go to the Logical Resource page and start live view of skin-surface temperature screening camera(s) that monitoring the same area with the above-mentioned people counting group. In this way, while monitoring the people amount in the monitored area, you can view the live view of the monitored area to get person information, including face picture, skin-surface temperature, wearing mask or not, etc. The latest person information will be displayed on the right in thumbnail format.

People Stayed

The amount of people who are currently inside the monitored area.

Remaining Capacity

The amount of people that can enter the monitored area. If the people stayed amount exceeds the number set when adding a people counting group, no people will be allowed to enter, and the green icon will turn to red for notification.

Edit Displayed Information

Hover the cursor on the people counting analysis window and click \mathbb{Z} to correct stayed people amount or edit descriptions and headlines.

- Correct People Amount: If the actual number of people stayed is different from the number displayed on the Control Client, you can enter the right people amount in the Correct People Number in Headline 01 field.
- Second Language: the Control Client supports displaying descriptions and headlines in two languages. Besides English, you can enter the descriptions and headlines in another language to display the information in two languages simultaneously.

Chapter 7 Start a Roll Call

After configuring the emergency solution, you can start a roll call by one click once an emergency happens.

In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Roll Call . Click In Emergency to display the data of emergency counting groups.



Figure 7-1 Data of Emergency Mustering

On the top left, the total number of persons in emergency counting groups are displayed. On the right of the total number of persons, the number of persons in danger and safe are both displayed. The persons in danger refer to persons who are still inside (checked in at the entrance point but did not check out at the exit point) the place where the emergency happens and the persons who did not check in at the entrance point. The persons who are safe refer to persons who have checked out at the exit point but not checked in at the mustering point and persons who have checked in at the mustering point.

The data of each emergency counting group is also displayed. You can click a group name to enter the page of the group for details. Click 2 to check in a person who shows at the mustering point but the person status is not Checked In.

Name (196)					 CarkforDanis plastatu 				tered Report
Desergency Counting Gos								14	Sections
								bear to	
	Public Public R	Address 1	- H.I	2 Marcal	Latingen I	Institut (Management, 1	Manual Charlos 7	Spectra 1
	12	-	1007344101	(blocker)	in a second				14
in Jangar I • Longar I • Longar I Mo 0 • Cont Alter Deat with 1 • Deated with 1 • Dea									

Figure 7-2 Data of an Emergency Counting Group

The virtual counting group refers to a group consisting of persons who are not added to any emergency counting group.

Perform the following operations if you need.

- Click End Emergency to end the emergency status of the platform.
- Click **Send Report** and select an email template to send the data of the emergency counting group to the recipients.

IINote

- It is extremely important to remember that the data displayed and the reports contained in the email can only ever be accurate if all users follow the conventions of the system. All users must read in and out of all controlled areas; running a logical anti-passback system can help to enforce this.
- During the emergency, editing the emergency solution is not allowed. You should end the emergency before editing it.

Chapter 8 Playback

You can view the recorded video files on the Monitoring module of the Control Client.

8.1 Normal Playback

You can search video files by area or camera for the Normal Playback and download found video files to local PC. You can also add a tag to mark important video footage, and so on.

IINote

- You can search video files by the time of the time zone where the device locates in, or by the time of the time zone where the PC running the Control Client locates in.
- Automatically converting daylight saving time to standard time is supported, or vice versa.
- Synchronous playback or asynchronous playback of devices in different time zones are supported.

8.1.1 Search Video File

You can search video files by camera, by area, or by time for normal playback. And you can also filter the searched video files by recording type, tag type, target type and storage location.

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow All Modules \rightarrow Surveillance \rightarrow Monitoring$.
- 2. Click Playback to enter the playback page.
- **3.** Drag the camera or area to the display window, or double-click the camera or area to play the recording of the specified camera(s) in selected window.

IINote

The playback window supports up to 16 channels.

Today's recorded video files of the selected camera will be played.

4. Click i on the toolbar to set the date and time.

IINote

In the calendar, the date with video files will be marked with a triangle.

After selecting the date and time, the matched video files will start playing in the display window.

5. Optional: Click **S** on the toolbar to select recording type, tag type, target type and storage location for playback.

IINote

To set the storage location for recording, refer to User Manual of HikCentral Professional Web Client.

8.1.2 Play Video File

After searching the video files for the normal playback, you can play the video via timeline or thumbnails.

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Monitoring .
- 2. Click the Playback tab to enter the playback page.
- **3.** Select a date with videos to start playing video and show the timeline after searching the video files.

IINote

The video files of different types are displayed in different colors on the timeline.

- **4.** Play video in specified time period by timeline or thumbnails.
 - Drag the timeline forward or backward to position the desired video segment.
 - Move the cursor over the timeline to take a quick view of video thumbnails (if supported by the device) and click the appearing thumbnail to play the specific video segment.

IINote

- Click I / on the right of the timeline bar, or use the mouse wheel to zoom in or zoom out the timeline.
- Click 🔟 / 🔟 to show or hide the thumbnail bar.
- Move the cursor to the top border of the thumbnail bar and drag to adjust the height of the thumbnails when the cursor changes into 🚆 . You can also click 📰 to lock the thumbnail bar above the playback timeline, and click 📰 to hide the thumbnail bar automatically.
- **5. Optional:** Move the cursor to the lower edge of the playback window to access the icons for further operations.

IINote

For details, refer to *Customize Icons on Playback Window* .

8.2 Start Playback in View Mode

You can quickly access the playback of the cameras managed in a view.

Before You Start

Make sure you have added a view. For details, refer to Manage View .

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Monitoring .
- 2. Click View on the left navigation bar.
- 3. Click the Playback tab to enter the playback page.
- 4. Click a view to quickly start the playback of all the cameras related to the view.

IINote

You can also quickly switch the added view from the drop-down view list above the display windows.

8.3 Synchronous Playback

You can play the video files of different cameras synchronously. Synchronous playback allows you to synchronize the display of video from multiple cameras.

Steps

iNote

Video files from up to 16 cameras can be played simultaneously.

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Monitoring .
- 2. Click the Playback tab to enter the playback page.
- 3. Start normal playback of at least two cameras.

IINote

For detailed configuration about normal playback and playback control, refer to <u>Normal</u> <u>Playback</u>. Some icons may not be available for synchronous playback.

- 4. Click Synchronous Playback on the playback toolbar to enable the synchronous playback.
- The cameras displayed in Playback will start synchronous playback.
- **5. Optional:** Click **Asynchronous Playback** on the playback toolbar to disable synchronous playback.
- **6. Optional:** Click and be to perform normal and reverse playback.
- **7. Optional:** Click and to perform single-frame normal and reverse playback.

IINote

- No more than 16 cameras are allowed in single-frame normal and reverse playback.
- If you pause one camera, others will be paused in the synchronous playback mode.
- **8. Optional:** Move the cursor to the lower edge of the playback window to access the icons for further operations.

IINote

For details, refer to *Customize Icons on Playback Window* .

8.4 Fisheye Playback

Fisheye playback function allows you to play the fisheye camera's video in fisheye dewarping mode. Fisheye dewarping mode refers to the process of perspective correction of an image, to reverse the effects of geometric distortions caused by the fisheye camera lens. Dewarping allows you to cover a wide area with a single device and have a normal view of an otherwise distorted or reversed image.

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Monitoring .
- 2. Click the Playback tab to enter the playback page.
- **3.** Select a fisheye camera from the camera list to start playback.

INote

For detailed configuration about playback and playback control, refer to Normal Playback .

- **4.** Move the cursor to the display window, and click i on the appearing toolbar to enter the fisheye dewarping mode.
- 5. Drag on the video to adjust the view angle.
- 6. Scroll the mouse wheel to zoom in or zoom out the view.

8.5 Create Zooming Area to View Detailed Playback

You can create a zooming area on the playback window (main window) and then the created area will be displayed in a new window beside. After that, you can view the overall playback image in the main window and view more detailed image of the created area in the new window.

Before You Start

You have added camera(s) to the Web Client. For details, refer to User Manual of HikCentral Professional Web Client.

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Monitoring .
- 2. Click i Monitoring on the left navigation bar.
- 3. Click the Playback tab to enter the playback page.
- 4. Select an camera from camera list.

IINote

You can enter a key word (supports fuzzy search) in the search box to search the target camera(s) quickly.

- 5. Drag or double click the selected camera to the display window to view playback.
- 6. Create a zooming area on the video to view detailed playback in a new window.
 - For a normal camera, click 🔳 and draw a rectangle on the video.




Figure 8-1 Zooming Area Window (Normal Camera)

IINote

Up to 5 rectangles can be added.

- For a fisheye camera, click and draw a rectangle on the video.



Figure 8-2 Dewarped Zooming Area Window (Fisheye Camera)

iNote

- Up to 8 rectangles can be added.
- For fisheye cameras, you can view the dewarped zooming image in the new playback window.

Zooming area(s) you have created will be displayed in the new playback window(s). **7. Optional:** Perform following operations according to your needs.

Add ZoomingPut the cursor on the main playback window and draw a new rectangle as
desired.

Delete Zooming Area	Move the cursor to a rectangle on the main playback window, and click 🔀 to delete the related zooming area.
Edit Zooming Area	Move the cursor to a rectangle on the main playback window, and drag its edge when the cursor turns to a double-headed arrow to adjust the size of zooming area.
Stop Playback	On the zooming area window, click 🔣 on the upper right corner to close the playback window.
	Note
	If you want to show the zooming area window again, you should click in / on the toolbar of the main playback window, and then drag the corresponding rectangle to a new playback window as desired.
Adjust Window Sequence	Drag the playback windows to the desired locations to adjust their sequences.

8.6 Customize Icons on Playback Window

You can customize the icons shown on the toolbar of the playback window, adjust the icon order and set whether to always display toolbar on the playback window.

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Management \rightarrow System .
- 2. Select Video → Toolbar .
- **3.** In **Playback Toolbar** section, add or remove the icons to show or hide the icons on the live view toolbar.
- 4. Customize playback toolbar.
 - Click an icon in the list to add it to the gray frame below to hide the icon. Icons in the gray frame will be hidden in the toolbar of the playback window.
 - Click the icon in the gray frame to add it back to the playback toolbar to show an icon on the toolbar.
- 5. Drag the icons in the icon list to adjust icon order.

Table 8-1 Icons	on Pla	yback To	olbar
-----------------	--------	----------	-------

•	Audio Control	Turn off/on the sound and adjust the volume.
۵	Capture	Take a snapshot of the current video and save in the current PC.

		Note After capturing a picture, a thumbnail will pop up on the upper-right corner. You can click Search by Picture to search the captured picture, archive, and identity verification related with the captured picture.
•	Print	Take a snapshot of the current video and print it. Note You can enter some descriptive information of the picture to be printed.
×	Clip	Clip the video files for current playback and save in the current PC. You can save the clipped video as evidence, and set the saving path for the clipped video files. For details about saving video files as evidence and setting saving path, see <u>Manual Recording</u> .
	Add Tag	Add custom tag for the video file to mark the important video point. You can also edit the tag or go to the tag position conveniently.
0	Lock Video	Lock the video file and set the locking duration to avoid deleting the video file and protect the video file from being overwritten when the HDD is full. Note For the camera imported from Remote Site, if the video files are stored on the encoding device locally, you cannot lock the video files.
٩	Digital Zoom	Zoom in or out the video for cameras that do not have their own optical zoom capabilities. Click again to disable the function. Note When in software decoding mode, you can also capture the zoomed in picture after enabling digital zoom function.
9	Export	Export the video files of the camera and save them to your PC or connected USB device. You can also save the video file as evidence, and set saving path for the video

		files. For details about saving video files as evidence and setting saving path, see <u>Manual Recording</u> .
8	Fisheye Expansion	Available for fisheye camera for entering the fisheye dewarping mode. See <i>Fisheye Playback</i> .
0	VCA Search	Display the VCA Search window. You can set VCA rule to search video files and filter the videos by VCA event types, including VCA Search, Intrusion Detection, and Line Crossing Detection. Refer to <u>Search VCA Event Related</u> <u>Video</u> for more details.
8	Camera Status	Show the camera's recording status, signal status, connection number, etc.
3	Stream Switch	Switch the stream to main stream, sub-stream (if supported), or smooth stream (if supported).
		If the device supports transcoding playback, start transcoding and you need to set the resolution, frame rate and bitrate for transcoding.
		Note
		 The smooth stream will show if device supports. You can switch to smooth stream when in low bandwidth situation to make playback more fluent. Only video files stored in DVR and I-series NVR support transcoding playback.
•	Display on Smart Wall	Click 📰 to view the playback on smart wall. See <u>Manage</u> <u>Smart Wall (Decoding Device)</u> for details.
8	Frame-Extracting Playback	Extract frames from the video and play the extracted images (frames) one by one.
(Visual Tracking	Track an individual (such as a suspect) across different areas without losing sight of the individual. See User Manual of HikCentral Professional Web Client and <u>Visual</u> <u>Tracking</u> for details about setting and performing visual tracking.
	Create Zooming Area	Create zooming area(s) on the video image to view detailed playback. See <u>Create Zooming Area to View</u> <u>Detailed Playback</u> for details.
54	Create Dewarped Zooming Area	Create dewardped zooming area(s) on the video image to view detailed playback. See <u>Create Zooming Area to View</u> <u>Detailed Playback</u> for details.

	Search by Picture	Search for the target person by the captured pictures. See <u>Search Captured Face Pictures and Related Videos</u> for details.
t _{eo}	Video Enhancement	Adjust the video image including brightness, saturation, etc.
•	Two-Way Audio	Start two-way audio with the camera to get the real-time audio from the device to realize voice talk with the person at the device.
ø	Rotate Image	Rotate a image.

IINote

The icons shown on the toolbar in the display window will vary with the device's capabilities.

6. Optional: Check Always Display Toolbar to always display the toolbar on the playback window.

7. Click Save to save the above settings.

Chapter 9 Visual Tracking

Visual tracking allows you to track an individual (such as a suspect) across different areas without losing sight of the individual.

You can perform visual tracking in both live view and playback. After entering the visual tracking mode, icons of associated cameras will be overlaid on the video image. Each icon corresponds to one adjacent camera that you can jump to.

For details about setting the camera's associated cameras for visual tracking, refer to the User Manual of HikCentral Professional Web Client.

9.1 Perform Visual Tracking in Live View

During live view, if the camera is configured with associated cameras for visual tracking, you can easily track the individual appeared by accessing the live video of adjacent cameras directly.

Steps

- 1. Enter the Monitoring module.
- 2. Start live view of one camera which is configured with visual tracking.
- 3. On the live view toolbar, click 🌆 to enter the visual tracking mode.

The live view of the current camera and the associated cameras will be displayed.

4. When the individual moves out of the camera's field of view, click the associated camera icon representing a link to jump to the live view of the associated camera.



Figure 9-1 Visual Tracking in Live View

The live view of the associated camera will be displayed in the middle. Meanwhile, the live view of the associated cameras (if configured) of this associated camera will show.

5. Optional: You can perform the following operations during visual tracking.

Stop Recording	On the toolbar, click 🛅 to stop recording video footage for the camera in the middle.
	Note
	By default, video recording automatically starts when entering visual tracking.
Capture a	On the toolbar, click 📷 to capture a picture for the camera in the middle.
Picture	After capture, you can click Search by Picture to perform further search.
	For searching captured picture, refer to <u>Search Captured Face Pictures</u> and Related Videos
	For searching archive, refer to <u>Archive Search</u> .
	For identity verification, refer to <i>Identity Verification</i> .
Show/Hide Camera Icon	On the toolbar, click 🏧 / 🔤 to show or hide the icons of the associated cameras.
Jump to Previous/Next	Click ← Previous or Next → to jump to the live view of previous or next camera.
Camera	or right corner to ovit the viewal tracking mode

6. Click Exit in the upper-right corner to exit the visual tracking mode.

i Note

In the pop-up window, you can click **OK** to save the recorded video file. Click **Cancel** or \mathbf{X} to discard the recorded video file and back to the live view window.

9.2 View Visual Tracking Video

During playback, if the camera is configured with associated cameras for visual tracking, you can easily track the individual appeared by accessing the recorded video of adjacent cameras directly.

Steps

1. Enter the Monitoring module.

- **2.** Start playback of the camera. Currently, you can access visual tracking during playback in the following modules:
 - In the Playback module, start playback of the camera which is configured with visual tracking and recording schedule. For details about starting playback, refer to <u>*Playback*</u>.
 - During live view, start instant playback of the camera which is configured with visual tracking and recording schedule. For details about starting instant playback, refer to *Live View*.
 - In the Video Search module, after searching the video footage of the camera which is configured with visual tracking and recording schedule, start playing the videos. For details, refer to <u>Video Search</u>.

- In the Alarm Center module, when checking the related video of the alarm source, start playback of the camera which is configured with visual tracking and recording schedule. For details, refer to Check Alarm and Event .
- In the Access Record Retrieval module, when checking the related video of the access point, start playback of the camera which is configured with visual tracking and recording schedule. For details, refer to Search Access Records .
- 3. On the playback toolbar, click m to enter the visual tracking mode.

The recorded video of the current camera and the associated cameras will be displayed.

4. When the individual moves out of the camera's field of view, click the associated camera icon representing a link to the next camera.



Figure 9-2 Visual Tracking in Playback

The recorded video of the associated camera will be displayed in the middle. Meanwhile, the recorded video of the associated cameras of this associated camera will show. 5. Optional: You can perform the following operations during visual tracking.

Stop Clipping On the toolbar, click **w** to stop clipping the video footage for the camera in

	the middle.
	Note
	By default, video clipping automatically starts when entering visual tracking.
Capture a Picture	On the toolbar, click to capture a picture for the camera in the middle. After capture, you can click Search by Picture to perform further search. For searching captured picture, refer to <u>Search Captured Face Pictures and</u> <u>Related Videos</u> . For searching archive, refer to <u>Archive Search</u> .

For identity verification, refer to *<u>Identity Verification</u>*.

Show/Hide Camera Icon	On the toolbar, click 🏧 / 🚾 to show or hide the icons of the associated cameras.
Jump to Previous/Next Camera	Click \leftarrow Previous or Next \rightarrow to jump to the playback of previous or next camera.

6. Click Exit in the upper-right corner to exit the visual tracking mode.

iNote

In the pop-up window, you can click **OK** to save the clipped video file. Click **Cancel** or \mathbf{X} to discard the clipped video file and back to the playback window.

Chapter 10 Manage Favorites

You can add and manage Favorites on the client. For camera(s) added to the Favorites, you can quickly view the live view or start the playback.

Before You Start

Make sure you have added camera(s) to area(s). Refer to the User Manual of HikCentral Professional Web Client for details.

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Monitoring .
- 2. Click Favorites on the left navigation bar.

IINote

In the Favorites list, two default root Favorites (**Favorites** and **Favorites Shared by Others**) are displayed. You can click to view the sub Favorites and cameras added in these two root Favorites.

3. Select a parent Favorites.

IINote

You can either select the root Favorites or the sub Favorites added under the root one.

- **4.** Add a Favorites under the parent Favorites.
 - 1) Click + .
 - 2) Enter the name for Favorites.
 - 3) **Optional:** Select a parent node from the drop-down list.
 - 4) Optional: Check Online Resource Only to display online resources only on the list.
 - 5) Select the camera(s) to be added to Favorites.
 - 6) Click Save.

iNote

Up to 5 levels of Favorites can be added.

5. Optional: Perform the following operations.

Edit Favorites	Select a Favorites, and click □ → Edit on the right side of Favorites' name to edit its name and add more camera(s) to it if needed.
Share Favorites	Select a Favorites, and click $\blacksquare \rightarrow$ Share on the right side of Favorites' name to share it with others.
	Note
	For details about adding user(s), refer to the User Manual of HikCentral Professional Web Client.

Delete Favorites	 Select a Favorites, and there are two methods to delete it. Click on the top of the Favorites list, and click OK. Click → Delete on the right side of Favorites' name.
View Live View/Playback of All Cameras	 When in Live View window, select a Favorites, and click → Play All to start viewing the live view of all the camera(s) added in Favorites. When in Playback window, select a Favorites, and click → Play All to start viewing the playback of all the camera(s) added in Favorites.
Search Camera in Favorites	Enter keywords in the search box above the Favorites list to search for the target camera(s) or Favorites.
Delete Camera in Favorites	Select a camera in Favorites, and click T to delete it.

Chapter 11 Add Web Page to Display Window

During the live view and video playback or when customizing the Control Panel, you can add web page(s) to a display window to view the online news, log into HikCentral Professional Web Client, etc.

Steps

1. In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Monitoring .

INote

For adding a web page when customizing the Control Panel, refer to <u>Customize Control Panel</u>.

- 2. Click Add Web Page Window on the left navigation bar.
- 3. In the Web Page window, enter the web site in the address bar.
- **4.** Press the Enter key to enter the corresponding web page.
- 5. Browse the contents on the web page.
- **6. Optional:** Perform the following operations.

Add More Web Page	Click Add Web Page Window on the navigation bar to add more web page(s).		
	I INote		
	Up to 64 web pages can be added.		
Refresh Web Page	Click 📴 to refresh the web page if needed.		
Add Web Page to Favorites	Click ■ → Add to Favorites , enter the name for Favorites, and click Add to add the current web page to Favorites.		
	I INote		
	You can check Set as Default Web Page to set the current web page as a default web page, and then when you add a new web page the next time, the default web page will pop up.		
Adjust Web Page Size	Click a web page, move the cursor to the boundary of the web page, drag the cursor when it turns to double arrow to adjust the size of web page.		
Close Web Page	Click I to close the current web page.		

Chapter 12 Customize Intelligent Monitoring Contents

Intelligent Monitoring displays the real-time captured pictures (of faces, human bodies, and vehicles) and the real-time events triggered by vehicles and persons. You can customize the contents to be displayed on this page.

Before You Start

Make sure you have added smart cameras and DeepinMind servers to the Web Client. For details, refer to the User Manual of HikCentral Professional Web Client.

Steps

- In the upper-left corner of Control Client, select
 → All Modules → Surveillance → Intelligent Monitoring to enter the Intelligent Monitoring page.
- 2. Click Set in the upper-right corner to show the Settings Panel.
- 3. Click Display Settings, and configure the related parameters.

Captured Object

Select Face and/or Human Body and/or Vehicle as captured object(s).

Event Settings

Events Triggered by Persons

Switch on **Events Triggered by Persons**, and select the event types such as **Captured Face** and **Matched Face**.

i Note

When selecting **Matched Face** as the event type, you should select one or more face comparison groups from the list below. For details about adding face comparison groups, refer to the *User Manual of HikCentral Professional Web Client*.

Events Triggered by Vehicles

Switch on **Events Triggered by Vehicles**, and select the event types including **Vehicle Matched** and **Vehicle Mismatched**.

iNote

When selecting **Vehicle Matched** as the event type, you should select one or more vehicle lists. For details about adding vehicle lists, refer to the *User Manual of HikCentral Professional Web Client*.

Pop-up Window

Switch on **Pop-up Window**, and select the needed condition(s) to enable pop-up notifications. For example, if you check **Abnormal Temperature**, a window will pop up in

the middle of the Intelligent Monitoring page when the device detects a person with abnormal temperature.

4. Click Feature Display, and configure the related parameters.

Person Features

Select what person feature(s) will be displayed in capture details. You can select up to 6 features (including features of human face and human body).

Vehicle Features

Select what vehicle feature(s) will be displayed in capture details. You can select up to 3 features.

5. Optional: Click **Monitoring Area** \rightarrow **1**, and select the specific camera(s) from the list to view the captured pictures and events of the selected camera(s).

INote

- By default, all resources are selected.
- You can also view the live view of the corresponding camera(s) in Live View.



Figure 12-1 Live View

6. Click Save to save the above settings.

You can view the real-time Today's Statistics on the top of the page, view the real-time captured pictures of persons and vehicles (if configured) on the left side of page, and view the person-triggered events and vehicle-triggered events (if configured) on the right side of the page.

IINote

The rule of counting Today's Statistics is as follows: Once there is a face, a human body, or a vehicle captured by the cameras, the number of faces, human bodies, and vehicles adds 1 in the platform. The same applies to the four types of events (Face Match Event, License Plate Matched, Frequently Appeared Persons, and Intelligent Cameras). Once a certain event is triggered, its number adds 1 in the platform.

7. Optional: Click a captured picture of a person or a vehicle to view its details (such as camera name and captured time), and perform more operations.

Operation	Function
Add Person	Add the person to the person list. For details, refer to <u>Add Mismatched Person to Person</u> <u>Group</u> .
Search by Picture	Search for the person in the captured pictures. For details, refer to <u>Search Face Pictures by</u> <u>Picture</u> .
Related Captures	Search for the related captures and videos. For details, refer to <u>Search Captured Face Pictures</u> and Related Videos.
More → Archive Search	Search for the archive of the current face picture. For details, refer to <u>Archive Search</u> .
More \rightarrow Identity Verification \rightarrow To be Verified	Verify the person's identity. For details, refer to Identity Verification .
More \rightarrow Identity Verification \rightarrow Target	Set the person as a comparison target. For details, refer to <i>Identity Verification</i> .
More → Download	Download the pictures and videos. For details, refer to <i>Manage Downloading Tasks</i> .

Table 12-1 Person Details

Table 12-2 Vehicle Details

Operation	Function
License Plate Retrieval	Search for vehicle passing records via the license plate number. For details, refer to Search for Vehicle Passing Records .
Download	Download the pictures and videos. For details, refer to <u>Manage Downloading Tasks</u> .

8. Optional: Click an event triggered by persons or vehicles to view its details (such as camera and capture time), and perform more operations.

IINote

Refer to the previous step for details.

9. **Optional:** Click in the upper-right corner to view the real-time captured pictures and events on an auxiliary screen.

Chapter 13 Video Search

The video files stored on local devices or Recording Server can be searched.

13.1 Search Video Footages by Time Range

You can search video footages by time range. Before search, you can configure the video segmentation settings to segment the matched video footage if the original video footage lasts too long. The segmented video files are shorter in terms of duration, which makes it easier for locating specific video information such as a recorded criminal incident. After search, you can export the matched video files to the local PC, and save them as evidence to the SFTP server.

Steps

- In the top left corner of the Control Client, select
 → All Modules → Investigation → Video Search .
- 2. Click Search Video Footage on the left.
- 3. Select Time Range as the search type.
- **4.** Set the time period for search in Time field.
 - Select the predefined time period in the drop-down list.
 - Select **Custom Time Interval** to specify the start time and end time for the search.

5. Select cameras.

- 1) Click 📭 in the camera panel.
- 2) Select a current site or Remote Site from the drop-down site list to show its cameras.
- 3) Check one or multiple cameras.
- 4) Click outside of the list to confirm.

iNote

- Up to 16 resources can be selected for search at one time.
- The icon 🚱 and 🚳 represent the current site and remote site respectively.
- 6. Optional: Move the cursor to the selected camera and click is to switch the stream type and storage location among Main Stream/Main Storage, Sub Stream/Main Storage, Main Stream/Auxiliary Storage, or Sub Stream/Auxiliary Storage.

IINote

You can move the cursor to e and batch switch the search condition, including stream type and storage location on the current/remote site. If the configured stream type or the storage location is not supported, it will not take effect.

- 7. Optional: Switch on Target Type and select the target type(s) as needed.
- 8. Optional: Switch on Video Segmentation to segment the matched video footage of each selected camera.

Segment

Set the number of video clips for equally segmenting the video footage of each selected camera. For example, if you set the segment value to *5*, the matched video footage of each selected camera will be divided into 5 segments, each of which equals in terms of time duration.

Interval (s)

The matched video footage of each selected camera will be segmented into video clips by the duration (unit: second) you set. For example, if you set 60 seconds as the duration for video segmentation, the matched video footage of each camera will be segmented into clips which last 60 seconds each.

Interval (min)

The matched video footage of each selected camera will be segmented into video clips by the duration (unit: minute) you set. For example, if you set 2 minutes as the duration for video segmentation, the matched video footage of each camera will be segmented into clips which last 2 minutes.

II Note

A few clip(s) may last less than the duration you set.

9. Click Search to find the related video footage.

The search results will be displayed and grouped by different cameras. You can switch between thumbnail and list mode to view.

- **10. Optional:** Segment the matched video footage of a specific camera if the video footage is still too long for locating the target video information.
 - 1) Click 🔳 to display the matched video footage in thumbnail mode, and then hover the cursor onto the thumbnail to show the Video Segmentation window.
 - 2) Hover the cursor onto the Video Segmentation window.

The field for setting the number of the segmented parts will be displayed.




Figure 13-1 Segment Matched Video Footage of a Specific Camera

3) Set the number of the segmented parts of the video footage, and then click **Video Segmentation** to segment the footage.

INote

You can segment the video footage to up to 100 parts.

- 11. Optional: Start remote playback of the searched video footage.
 - For list mode, click the item in Time Range column.
 - For thumbnail mode, click the image of the found result.
 - ζ.

Play the previous video footage among the searched results.

5

Play the next video footage among the searched results.

Play in Order

After playing the current video footage, continue to play the next one automatically.

IINote

- Refer to *Normal Playback* for more details about playback.
- On the playback toolbar, click into the visual tracking mode. For details, refer to <u>View</u>
 <u>Visual Tracking Video</u>.

- **12. Optional:** Export the matched video footage to local storage.
 - During playback, click 💽 on the toolbar to export the current video footage.
 - Select the video footage and click **Export** to export all the selected video footage.
 - 1) **Optional:** For downloading single video footage, set the time range of the video footage to download.
 - 2) Set the file format of the exported file.

MP4

MP4 format supports encryption. You can set a password to encrypt the video footage for security purpose.

Only VSPlayer supports playing video footage in MP4 format. You can check **Download VSPlayer** to download the player when exporting video footage.

AVI

Besides VSPlayer, other players also support playing the video footage in AVI format. You can check **Download VSPlayer** to download the player when exporting the video footage.

EXE

Package the video footage with the VSPlayer into one EXE file. The selected video footage of one camera will be merged to one MP4 file.

After downloading, double-click the EXE file and the VSPlayer will launch. The merged video footage of different cameras will be displayed in the playlist.

IINote

Up to 16 cameras can be selected to export their video footage in EXE format for one time.

3) **Optional:** If you select the format as MP4 or AVI, you can check **Merge Video Files** to merge the selected video footage of the same camera to one video file.

i Note

Up to 2 GB of video footage can be merged.

4) **Optional:** Check **Save to Evidence Management Center** and set the required information for the evidence.

i Note

- You should have enabled evidence collection on the Web Client. For details, see the *User Manual of HikCentral Professional Web Client*.
- For details about setting the required information for evidence, see <u>Save Found Video</u> <u>Footage as Evidence</u>.

5) Set the saving path to store the exported video footage.

6) Click Save to add the exporting task to the download center.

IINote

For details about managing the exporting tasks, refer to Manage Downloading Tasks .

13.2 Search Tagged Video Footages

You can search for the camera's tagged video footage. After search, you can export the matched video footage to the local PC and save the video footage as evidence to the SFTP server.

Steps

IINote

For adding tag to the video file, refer to *Play Video File*.

- In the top left corner of Control Client, select Investigation → Video
 Search .
- 2. Click Search Video Footage on the left.
- 3. Select Tag as the search type.
- 4. Set the time period for search in Time field.
 - Select the predefined time period in the drop-down list.
 - Select **Custom Time Interval** to specify the start time and end time for the search.
- 5. Select cameras.
 - 1) Click 📭 in the camera panel.
 - 2) Select a current site or Remote Site from the drop-down site list to show its cameras.
 - 3) Check one or multiple cameras.
 - 4) Click outside of the list to confirm.

IINote

- Up to 16 resources can be selected for search at the same time.
- 6. Optional: Move the cursor to the selected camera and click 🔳 to switch the stream type and storage location among Main Stream/Main Storage, Sub Stream/Main Storage, Main Stream/ Auxiliary Storage, or Sub Stream/Auxiliary Storage.

IINote

You can move the cursor to and batch switch the search condition, including stream type and storage location on the current/remote site. If the configured stream type or the storage location is not supported, it will not take effect.

7. Select the tag type.

Manually Added Tag

The custom tag which is added during video playback.

Event Triggered Tag

The tag which is created when a certain event happens.

INote

Before selecting this tag type, you should have configured the linkage action (creating tag) for certain events. For details, refer to the user manual of the Web Client.

- **8. Optional:** Enter a keyword of the tag name.
- **9.** Click **Search** to find the related video footage.

The search results will be displayed and grouped by different cameras. You can switch between thumbnail and list mode to view.

- **10. Optional:** Start remote playback of the searched video footage.
 - For list mode, click the item in Time Range column.
 - For thumbnail mode, click the image of the found result.

ζ.

Play the previous video footage among the searched results.

5

Play the next video footage among the searched results.

Play in Order

After playing the current video footage, continue to play the next one automatically.

INote

- Refer to *Normal Playback* for more details about playback.
- On the playback toolbar, click to enter the visual tracking mode. For details, refer to <u>View</u>
 <u>Visual Tracking Video</u>.

11. Optional: Export the found video footage to local storage.

- During playback, click 🔝 to export the current video footage.
- Select the video footage and click **Export** to export all the selected video footage.
- 1) **Optional:** For exporting single video footage, set the time range of the video footage for export.
- 2) Set the file format of the exported file.

MP4

MP4 format supports encryption. You can set a password to encrypt the video footage for security purpose.

Only VSPlayer supports playing video footage in MP4 format. You can check **Download VSPlayer** to download the player when exporting video footage.

AVI

Besides VSPlayer, other players also support playing the video footage in AVI format. You can check **Download VSPlayer** to download the player when exporting the video footage.

EXE

Package the video footage with the VSPlayer into one EXE file. The selected video footage of one camera will be merged to one MP4 file.

After downloading, double-click the EXE file and the VSPlayer will launch. The merged video footage of different cameras will be displayed in the playlist.



Up to 16 cameras can be selected to export their video footage in EXE format for one time.

3) **Optional:** If you select MP4 or AVI as the format, you can check **Merge Video Files** to merge the selected video footage of the same camera to one video file.

INote

Up to 2 GB of video footage can be merged.

4) **Optional:** Check **Save to Evidence Management Center** and set the required information for the evidence.

INote

- You should have enabled evidence collection on the Web Client. For details, see the *User Manual of HikCentral Professional Web Client*.
- For details about setting the required information for evidence, see <u>Save Found Video</u> <u>Footage as Evidence</u>.

5) Set the saving path to store the exported video footage.

6) Click **Save** to add the exporting task to the download center.

INote

For details about managing the exporting tasks, refer to Manage Downloading Tasks .

13.3 Search Locked Video Footages

You can search for the camera's locked video footage. After search, you can export the matched video footage to the local PC and save the video footage as evidence to the SFTP server.

Steps

Note
For locking the video file, refer to <u>Normal Playback</u> .
 In the top left corner of the Control Client, select All Modules → Investigation → Video Search .

- 2. Click Search Video Footage on the left.
- 3. Select Locked as the search type.
- 4. Set the time period for search in Time field.
 - Select the predefined time period in the drop-down list.

- Select **Custom Time Interval** to specify the start time and end time for search.

5. Select cameras.

- 1) Click 📭 in the camera panel.
- 2) Select a current site or Remote Site from the drop-down site list to show its cameras.
- 3) Check one or multiple cameras.
- 4) Click outside of the list to confirm.

IINote

- Up to 16 resources can be selected for search at the same time.
- The icon 🚱 and 🚳 represent the current site and remote site respectively.
- Optional: Move the cursor to the selected camera and click to switch the stream type and storage location among Main Stream/Main Storage, Sub Stream/Main Storage, Main Stream/ Auxiliary Storage, or Sub Stream/Auxiliary Storage.

iNote

You can move the cursor to and batch switch the search condition, including stream type and storage location on the current/remote site. If the configured stream type or the storage location is not supported, it will not take effect.

7. Click Search to find the related video footage.

The search results will be displayed and grouped by different cameras. You can switch between thumbnail and list mode to view.

- **8. Optional:** Start remote playback of the searched video footage.
 - For list mode, click the item in Time Range column.
 - For thumbnail mode, click the image of the searched result.

X.

Play the previous video footage among the searched results.

>

Play the next video footage among the searched results.

Play in Order

After playing the current video footage, continue to play the next one automatically.

IINote

- Refer to *Normal Playback* for more details about playback.
- On the playback toolbar, click to enter the visual tracking mode. For details, refer to <u>View</u>
 <u>Visual Tracking Video</u>.
- **9. Optional:** Export the found video footage to local storage.
 - During playback, click 💽 to export the current video footage.
 - Select the video footage and click **Export** at the upper-right side to export all the selected video footage.
 - 1) **Optional:** For exporting single video footage, set the time range of the video footage for export.

2) Set the file format of the exported file.

MP4

MP4 format supports encryption. You can set a password to encrypt the video footage for security purpose.

Only VSPlayer supports playing video footage in MP4 format. You can check **Download VSPlayer** to download the player when exporting the video footage.

AVI

Besides VSPlayer, other players also support playing the video footage in AVI format. You can check **Download VSPlayer** to download the player when exporting the video footage.

EXE

Package the video footage with the VSPlayer into one EXE file. The selected video footage of one camera will be merged to one MP4 file.

After exporting, double-click the EXE file, and then the VSPlayer will launch. The merged video footage of different cameras will be displayed in the playlist.

IINote

Up to 16 cameras can be selected to export their video footage in EXE format for one time.

3) **Optional:** If you select the format as MP4 or AVI, you can check **Merge Video Files** to merge the selected video footage of the same camera to one video file.

INote

Up to 2 GB of video footage can be merged.

4) **Optional:** Check **Save to Evidence Management Center** and set the required information for the evidence.

INote

- You should have enabled evidence collection on the Web Client. For details, see the *User Manual of HikCentral Professional Web Client*.
- For details about setting the required information for evidence, see <u>Save Found Video</u> <u>Footage as Evidence</u>.

5) Set the saving path to store the exported video footage.

6) Click Save to add the exporting task to the download center.

IINote

For details about managing the exporting tasks, refer to Manage Downloading Tasks .

13.4 Search Video/Picture/Audio Stored on Dock Station

The dock station is a data collector which can automatically detect and back up law-enforcement data and evidence data (including video footage, pictures, and audio files) from body camera(s) connected to it. You can search these data via the Control Client. After search, you can lock and unlock the matched data.

Before You Start

Make sure you have added dock station(s) to the platform. For details, see the User Manual of HikCentral Professional Web Client.

Steps

- **1.** In the top left corner of Home page, select $\blacksquare \rightarrow$ Investigation \rightarrow Video Search .
- 2. Click Report POS/ATM Event Search on the left side of the page to enter the Device Video Search page.
- 3. Select Dock Station as the search type.
- **4.** Set the time period for search in Time field.
 - Select the predefined time period in the drop-down list.
 - Select **Custom Time Interval** to specify the start time and end time for the search.
- 5. Select dock station group(s).

IINote

Dock station group is a group of persons (usually police officers). Only when the persons are added to the dock station, can the data in their body cameras be backed up to the dock station. For selecting dock station group(s) in this step, when a dock station group is selected, the data backed up from the body camera(s) of the persons in the selected dock station group will be searched.

- 6. Hover your cursor over 😑 on the right of **Dock Station Group**, and select storage location between Backup Server and Device.
- 7. Select a file type from the File drop-down list.
- 8. Click Search.

The matched video files, audio files, and pictures will be displayed by person. You can display the result in thumbnail mode or list mode.

- **9.** Click the matched file to play the video/audio file or view the picture.
- **10. Optional:** Perform the following operations.

Export Single File to Local	After opening the matched file, click 🌇 and then set the required information to export it to the local PC.
PC	Note

For details about the required information for exporting, see <u>Search</u> <u>Video Footages by Time Range</u>.

Batch Export Files to Local	Select the matched files, click Export and then set the required information for exporting to export the files to local PC.
PC	I INote
	For details about the required information for exporting, see <u>Search</u>
	<u>Video Footages by Time Range</u>
Lock File	After opening the matched file, click 🔚 to lock the file in order to prevent it from being overwritten, modified or deleted.

13.5 Search Transaction Event Triggered Video Footage

You can search for the video footage triggered by transaction event which contains POS information. After search, you can export the matched video footage to the local PC or save it as evidence to the SFTP server.

Steps

- In the top left corner of Control Client, select Search .
 Search .
- 2. Click 📰 Search Video on Device on the left.
- 3. Select Transaction Event as the search type.
- **4.** Set the time period for search in Time field.
 - Select the predefined time period in the drop-down list.
- Select **Custom Time Interval** to specify the start time and end time for the search.
- 5. Enter the keywords that are contained in the POS information.

IINote

- You can enter up to three keywords, and you should separate each one with a comma.
- If you enter more than one keyword for search, you can select "|" to search the POS information containing any of the keywords, or select "&" to search the POS information containing all keywords.
- 6. Optional: Select Case Sensitive to search the POS information with case-sensitivity.
- 7. Select the device and camera in the Camera field to search the transaction information.
- 8. Optional: Select a camera, move the cursor to and click it to switch the stream type and storage location among Main Stream/Main Storage, Sub Stream/Main Storage, Main Stream/Auxiliary Storage, or Sub Stream/Auxiliary Storage.

INote

You can move the cursor to and batch switch the search condition, including stream type and storage location on the current/remote site. If the configured stream type or the storage location is not supported, it will not take effect.

9. Click **Search** to find the related video footage.

The search results will be displayed and grouped by different cameras. You can switch between thumbnail and list mode to view.

10. Optional: Start remote playback of the searched video footage.

- For list mode, click the item in Time Range column.
- For thumbnail mode, click the image of the searched result.

ζ

Play the previous video footage among the searched results.

Ş

Play the next video footage among the searched results.

Play in Order

After playing the current video footage, continue to play the next one automatically.

iNote

- Refer to *Normal Playback* for more details about playback.
- On the playback toolbar, click to enter the visual tracking mode. For details, refer to <u>View</u>
 <u>Visual Tracking Video</u>.
- **11. Optional:** Export the searched video footage to local storage.
 - During playback, click 🔝 to export the current video footage.
 - Select the video footage and click **Export** to export all the selected video footage.
 - 1) **Optional:** For exporting single video footage, set the time range of the video footage for export.
 - 2) Set the file format of the exported file.

MP4

MP4 format supports encryption. You can set a password to encrypt the video file for security purpose.

Only VSPlayer supports playing video files in MP4 format. You can check **Download VSPlayer** to download the player with the video files.

AVI

Besides VSPlayer, other player also supports playing the video files in AVI format.

You can check **Download VSPlayer** to download the player with the video files.

EXE

Package the video files with the VSPlayer into one EXE file. The selected video footage of one camera will be merged to one MP4 file.

After downloading, double click the EXE file and the VSPlayer will launch. The merged video files of different cameras will be displayed in the playlist.

iNote

Up to 16 cameras can be selected to download in EXE format for one time.

3) **Optional:** If you select the format as MP4 or AVI, you can check **Merge Video Files** to merge the selected video footage of the same camera to one video file.

IINote

Up to 2 GB of files can be merged.

4) **Optional:** Check **Save to Evidence Management Center** and set the required information for the evidence.

INote

- You should have enabled evidence collection on the Web Client. For details, see the *User Manual of HikCentral Professional Web Client*.
- For details about setting the required information for evidence, see <u>Save Found Video</u> <u>Footage as Evidence</u>.

5) Set the saving path to store the exported video files.

6) Click **Save** to add the downloading task to the download center.

i Note

For details about managing the downloading tasks, refer to Manage Downloading Tasks .

13.6 Search ATM Event Triggered Video Footage

You can search for the video footage triggered by ATM event, such as transactions and other operations on the ATM. After search, you can save the matched video footage to the local PC and save it as evidence to the SFTP server.

Steps

- In the top left corner of Control Client, select Search .
 Search .
- 2. Click 🔚 Search Video on Device on the left.
- **3.** Select the search type as **ATM Event**.
- **4.** Set the time period for search in Time field.
 - Select the predefined time period in the drop-down list.
 - Select **Custom Time Interval** to specify the start time and end time for the search.
- 5. Enter the card number that is contained in the ATM information.
- 6. Select the device and camera to search the ATM information in the Camera field.
- 7. Optional: Select a camera, move the cursor to and click it to switch the stream type and storage location among Main Stream/Main Storage, Sub Stream/Main Storage, Main Stream/ Auxiliary Storage, or Sub Stream/Auxiliary Storage.

IINote

You can move the cursor to and batch switch the search condition, including stream type and storage location on the current/remote site. If the configured stream type or the storage location is not supported, it will not take effect.

8. Click Search.

The search results will be displayed and grouped by different cameras. You can switch between thumbnail mode and list mode to view.

- **9. Optional:** Start remote playback of the searched video footage.
 - For list mode, click the item in Time Range column.
 - For thumbnail mode, click the image of the searched result.

Κ

Play the previous video footage among the searched results.

5

Play the next video footage among the searched results.

Play in Order

After playing the current video footage, continue to play the next one automatically.

iNote

- Refer to *Normal Playback* for more details about playback.
- On the playback toolbar, click to enter the visual tracking mode. For details, refer to <u>View</u> <u>Visual Tracking Video</u>.
- **10**. **Optional:** Download the matched video footage to local storage.
 - During playback, click 💽 to download the current video footage.
 - Select the video footage and click **Export** to export all the selected video footage.
 - 1) **Optional:** For downloading single video footage, set the time range of the video footage to download.
 - 2) Set the file format of the downloaded file.

MP4

MP4 format supports encryption. You can set a password to encrypt the video file for security purpose.

Only VSPlayer supports playing video files in MP4 format. You can check **Download VSPlayer** to download the player with the video files.

AVI

Besides VSPlayer, other player also supports playing the video files in AVI format.

You can check **Download VSPlayer** to download the player with the video files.

EXE

Package the video files with the VSPlayer into one EXE file. The selected video footage of one camera will be merged to one MP4 file.

After downloading, double click the EXE file and the VSPlayer will launch. The merged video files of different cameras will be displayed in the playlist.

iNote

Up to 16 cameras can be selected to download in EXE format for one time.

3) **Optional:** If you select the format as MP4 or AVI, you can check **Merge Video Files** to merge the selected video footage of the same camera to one video file.

iNote

Up to 2 GB of files can be merged.

4) **Optional:** Check **Save to Evidence Management Center** and set the required information for the evidence.

INote

- You should have enabled evidence collection on the Web Client. For details, see the *User Manual of HikCentral Professional Web Client*.
- For details about setting the required information for evidence, see <u>Save Found Video</u> <u>Footage as Evidence</u>.

5) Set the saving path to store the downloaded video files.

6) Click **Save** to add the downloading task to the download center.

i Note

For details about managing the downloading tasks, refer to Manage Downloading Tasks .

13.7 Search VCA Event Related Video

You can search video files where VCA events occur. And you can play or download the found video files. The VCA events include motion detection, intrusion, and line crossing.

Steps

iNote

- This function should be supported by the device.
- Video files stored on a Hybrid Storage Area Network do not support VCA event search.

1. Access the VCA Event search page and three ways are selectable.

Access from Live View Page	 a. Enter the Live View page, and start the live view of the camera (refer to <u>Start Live View in Area Mode</u>. b. Move the cursor to the display window and click it to pop up the VCA Event search page.
Access from Playback Page	 a. Enter the Playback page, and start playback of the camera (refer to <i>Normal Playback</i>). b. Move the cursor to the display window and click it to pop up the VCA Event search page.
Access from VCA Search Page 2. Set the time period for Select the prodefin	In the top left corner of Control Client, select $\blacksquare \rightarrow$ Investigation \rightarrow Video Search $\rightarrow \blacksquare$ VCA Search . For search in Time field.

- Select the predefined time period in the drop-down list.
- Select **Custom Time Interval** to specify the start time and end time for the search.

3. Select the site (current site or Remote Site) and then select the camera to search the video where the VCA event occurs.

IINote

Perform this step when you access the VCA Event search page from the Video Search module.

- **4.** Select the VCA type, and draw the detection region or line for search.
 - **Dynamic Analysis:** Drag the cursor on the video image to set the grid rectangle as the detection region for searching the video footage of the motion detection events that occurred within the region.
 - Line Crossing: Drag the cursor on the video image to set the detection line for searching the video footage of the line crossing events that occurred on the line.
 - Intrusion Detection: Drag the cursor on the video image to draw the vertex(es) of the detection region and then right-click to finish drawing. The settings is for searching the video footage of the intrusion events that occurred within the region.
- 5. Optional: Click 💼 to delete the drawn region or line.
- **6.** Adjust the sensitivity for detecting the event.

IINote

The larger the sensitivity is, the more sensitive the detection is.

7. Click **Search** to find the related video footage.

The search results will be displayed and grouped by different cameras. You can switch between thumbnail and list mode to view.

- 8. Optional: Start remote playback of the searched video footage.
 - For list mode, click the item in Time Range column.
 - For thumbnail mode, click the image of the searched result.

K

Play the previous video footage among the searched results.

5

Play the next video footage among the searched results.

Play in Order

After playing the current video footage, continue to play the next one automatically.

IINote

- Refer to *Normal Playback* for more details about playback.
- On the playback toolbar, click to enter the visual tracking mode. For details, refer to <u>View</u>
 <u>Visual Tracking Video</u>.
- 9. Optional: Download the searched video footage to local storage.
 - During playback, click 💽 to export the current video footage.
 - Select the video footage and click **Export** to export all the selected video footage.
 - 1) **Optional:** For exporting single video footage, set the time range of the video footage to export.

2) Set the file format of the exported file.

MP4

MP4 format supports encryption. You can set a password to encrypt the video file for security purpose.

Only VSPlayer supports playing video files in MP4 format. You can check **Download VSPlayer** to download the player with the video files.

AVI

Besides VSPlayer, other player also supports playing the video files in AVI format.

You can check **Download VSPlayer** to download the player with the video files.

EXE

Package the video files with the VSPlayer into one EXE file. The selected video footage of one camera will be merged to one MP4 file.

After downloading, double click the EXE file and the VSPlayer will launch. The merged video files of different cameras will be displayed in the playlist.

INote

Up to 16 cameras can be selected to download in EXE format for one time.

3) **Optional:** If you select the format as MP4 or AVI, you can check **Merge Video Files** to merge the selected video footage of the same camera to one video file.

IINote

Up to 2 GB of files can be merged.

4) **Optional:** Check **Save to Evidence Management Center** and set the required information for the evidence.

IINote

- You should have enabled evidence collection on the Web Client. For details, see the *User Manual of HikCentral Professional Web Client*.
- For details about setting the required information for evidence, see <u>Save Found Video</u> <u>Footage as Evidence</u>.

5) Set the saving path to store the exported video files.

6) Click Save to add the downloading task to the download center.

IINote

For details about managing the downloading tasks, refer to Manage Downloading Tasks .

Chapter 14 Manage Downloading Tasks

You can view the ongoing or completed downloading task information and manage all the tasks (e.g., video downloading, vehicle information downloading), such as starting, stopping, deleting and so on, in the Download Center.

Steps

In the top left corner of Control Client, select
 → All Modules → Management → Download Center .

Constanting (2	© SheAA - @	fase. () Den	4 . L C	.d. Doenka	d Pla.	Seech -	
t tylendrog m	Name		See	Status	Operation		
🕻 Complete (D.							

Figure 14-1 Download Center

2. Check the download tasks.

Check Downloading Task	Click the Downloading tab to check the downloading tasks.
Check Uploading Task	Click the Uploading tab to check the evidence which is being uploaded from the local PC to the resource pool.
	II Note
	For details about saving video footage as evidence, see Evidence
	Management Center .

Check Complete Task Click the **Complete** tab to check the completed tasks. **3. Optional:** Perform the following operation(s) for the tasks.

Pause Downloading	Click Cl
Resume Downloading	Click Ito resume the downloading, or click Start All to resume all the paused tasks.
Arrange Time for Auto-download	 You can arrange an off-peak time period to automatically download files to avoid network congestion under low network bandwidth. a. Click the Downloading tab. b. Check Select Period to select one or more time periods and customize the corresponding time period for automatically downloading.
Delete Downloading Task	 Select a task and then click to remove the downloading task, or click Delete All to delete all the downloading records. For complete downloading task, you can also select to delete the downloaded video files.
View Downloaded Video	For complete downloading task, click 💿 in Operation column to view the downloaded video files.
Select Saving Path for the Video File Optional: Click Downloa	For complete downloading task, select one or multiple tasks and then click Save As and select the saving path for the video files. d Player to download the player to your PC for playing the downloaded

^{4.} Optional: Click **Download Player** to download the player to your PC for playing the downloaded video files.

Chapter 15 Map Management

After properly configuring the map settings via the Web Client and enabling the map function on Monitoring module, you can view and manage the map, such as zooming in or zooming out the map, locating the resources on the map. You can view and operate the added resources on the map, such as getting the live view and playback of the cameras, UVSSs, and doors, setting the arming control for cameras, alarm inputs, UVSSs, and doors, and so on.

IINote

- If the GIS map doesn't show properly, all the current site's and Remote Site's E-map thumbnails are displayed. Click one E-map to view details.
- If you enable the GIS map function of the Central System via Web Client, you enter the configured GIS map. All the current site's and Remote Site's E-map thumbnails are displayed under the GIS map. Click one E-map to view details.

15.1 Operate Hot Spot

The resources (including cameras, alarm inputs, alarm outputs, access points, elevators, radars, UVSS, and digital signage) added on the map are called the hot spots. The hot spots show the locations of the resources. You can operate the hot spot, such as starting live view of the camera, UVSS, and door, arming or disarming the resources.

15.1.1 Preview Hot Spot

You can view locations of hot spots including cameras, alarm inputs, alarm outputs, access points, elevators, radars, sites, Under Vehicle Surveillance Systems (UVSS), etc. on the map. Also, you can set the arming control and view history alarms of surveillance scenarios through the hot spots.

Before You Start

Configure the map settings via the Web Client. For details, see User Manual of HikCentral Professional Web Client.

Steps

- **1.** In the top left corner of Control Client, select $\mathbb{H} \rightarrow \text{All Modules} \rightarrow \text{Surveillance} \rightarrow \text{Monitoring}$.
- 2. Select an area on the left, and double-click
- 3. Optional: Perform the following operations on the map.

Select Multiple Resources Click **(**and draw a rectangle on the map to select multiple resources.

Drag Resource(s) on Map to Display	Select one or multiple resources on map and drag it/them to the display window in Live View or Playback.
Real-Time Display of Face Comparison/Access Control/Vehicle List	Click Live View and select the item(s) to display real-time related captured face picture, access event, and vehicle list on the map.
More Tools	 Add a label on map. Capture a picture. Print the current map.

2D/3D: Switch the displaying dimension of the map.

: Search hot spot or location on the map.

Display Map on Smart Wall Click 🎆 to display the map on smart wall. For details, see <u>Display</u> Map on Smart Wall .

4. Click the hot spot to open the dialog which displays its related functions.

IINote

- If there is an alarm triggered on the hot spot, the hot spot icon will turn into red alarm mode
 Click the red icon, and you can view the detailed alarm information.
- Click parking lot data, a panel of parking lot details will pop-up. You can view detailed parking lot information such as parking space occupacy rate and parking floor details.

5. Operate in the dialog.

- For camera and UVSS hot spot: Check the live view and playback of the camera, view its status, area, and remark, set the arming control, and view the history alarms.

Note

- To view the live view and playback of the camera, the user should be assigned with permissions of live view and playback of the camera. For details, refer to the User Manual of HikCentral Professional Web Client.
- For details about arming control, see Arm or Disarm Hot Spot .
- For details about viewing history alarms, see View History Alarm .
- For alarm input hot spot: View its status, area, and remark, set the arming control, and view the history alarms.
- For alarm output hot spot: Turn on or off the linked alarm output.
- For access point hot spot: View the access point status, check the live view and playback of the access point's related camera(s), view the access point's basic information, control the door status, set the arming control, and view the history alarms and access records.
- For elevator hot spot: View the elevator status, area and remark, check the live view and playback of the elevator's related camera(s), control the floor status, set the arming control, and view the history alarms and access records.
- For radar hot spot: View the radar status, area and remark, check the live view and playback of the radar's related camera(s), set the arming control, view the history alarms.

- For radar PTZ camera hot spot: View camera's field of view and view the object's moving pattern.
- For site hot spot: View the site's resources and alarms which are not handled.
- For partition hot spot: Set the arming control including alarm clearing, disarming, away arming, stay arming, instant arming. For details, refer to <u>Arm or Disarm Hot Spot</u>.
- For parking lot hot spot: Click a certain floor and you will go to the paking lot management module so you can view the details of the the parking floor in the parking lot.

Hover your cursor on a parking lot, you can view the details of the parking lot. If nothing appears, you can click **Configure Now** to configure the parking lot.

15.1.2 Arm or Disarm Hot Spot

You can arm or disarm the hot spots via the arming control function. After arming the device, the current Control Client can receive the triggered alarm information from the hot spot.

Before You Start

Configure the map settings via the Web Client. For details, see User Manual of HikCentral Professional Web Client.

Steps

1. In the top left corner of Control Client, select $\blacksquare \rightarrow All Modules \rightarrow Surveillance \rightarrow Monitoring$.

- 2. Click Select Map on the top left to display the map(s) of an area.
- 3. Optional: If an area has multiple maps, click to select a map.
- 4. Click the hot spot.

A window on which the related functions of the hot spot display is opened.

5. Click Arm/Disarm to arm/disarm the hot spot.

15.1.3 View History Alarm

When an alarm is triggered, it will be recorded in the system. You can check the history log related to an alarm, including the alarm source details, alarm category, alarm triggered time, etc.

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Monitoring .
- 2. Click the hot spot.

A dialog pops up on which the related functions of the hot spot display.

- 3. Click 🔤 to enter the event and alarm search page.
- 4. Search history alarms of the hot spot. See Search Event and Alarm Logs for details.

15.1.4 Broadcast via Hot Spot

You can broadcast via hot spot through real-time speaking or playing the saved audio files.

Before You Start

Make sure you have added broadcast resources on the map.

Steps

- **1.** In the top left corner of Home page, select $\boxplus \rightarrow$ All Modules \rightarrow Map \rightarrow Map Monitoring .
- **2.** In the top left corner of Control Client, select $\mathbb{H} \rightarrow All Modules \rightarrow Surveillance \rightarrow Monitoring$.
- 3. Select an area on the left, and double-click
- 4. Optional: Click By Speaker Unit.
- 5. Select the speaker unit(s) for broadcast.

IINote

You should select the online speaker unit(s).

- Check Group, and select one or more speaker units from speaker unit group(s).

INote

You can click **Display Speaker Units Not Grouped** to display the speaker unit(s) that are not grouped.

- Check **Area**, and select one or more speaker units from the area(s) where the speaker units are added.
- 6. Select Speak or Play Audio as the broadcast mode.

iNote

Speak

Speak in real-time, and the audio will be recorded and uploaded to the server.

Play Audio

Play the files saved in the server.

7. Optional: If you select Play Audio as the adding mode, you can search or select a desired audio file to play.

IINote

Click **Download** to download a selected audio file. The speed of playing the audio file will be faster if you downloaded them.

8. Click Start.

- 9. Optional: Click By Device.
- **10.** Select an existing device group or click \Box to add a device group if needed, and then click **Add** to select the device(s) to broadcast to.
- **11.** Start or stop broadcasting.

	Note You can view the real-time broadcast status.	
Stop All	Click Stop All to stop broadcasting to the selected device(s).	

15.2 Preview Hot Region

The hot region function links a map to another map. When you add a map to another map as a hot region, an icon of the link to the added map is shown on the main map. The added map is called child map while the map to which you add the hot region is the parent map.

Before You Start

Configure the map settings via the Web Client. For details, see User Manual of HikCentral Professional Web Client.

Steps

1. In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Monitoring .

- 2. Click Select Map on the top left to display the map(s) of an area.
- 3. Optional: If an area has multiple maps, click a map to select it.
- **4.** Click a hot region on the map to enter the map of the hot region.

15.3 Preview Resource Group

During displaying map, you can view locations and regions of the resource groups, including people counting group, multi-door interlocking group, and anti-passback group. You can also perform further operations on the resources in the group.

INote

Make sure you have configured the required resource group and map settings via the Web Client. For details, see *User Manual of HikCentral Professional Web Client*.

Enter the Monitoring module and display the map. You can locate the resource group and view related alarms on the map.

- People Counting Group: You can view the real-time number of people entered, exited the region, or stayed in the region. Meanwhile, when an alarm is triggered in the region (such as people amount more/less than threshold), the region of the group will be highlighted on the map to notify the user on the Control Client.
- Pathway Analysis Group: You can view the real-time number of people walking by in the Monitoring module on the Control Client.
- Anti-Passback Group: When an anti-passback alarm is triggered by the doors in the group, the region of the group will be highlighted on the map and you can view the real-time alarms triggered in the region in the Monitoring module on the Control Client.

- Multi-Door Interlocking Group: When multi-door interlocking alarm is triggered by the doors in the group, the region of the group will be highlighted on the map and you can view the real-time alarms triggered in the region in the Monitoring module on the Control Client.
- Entry & Exit Counting Group: You can view the real-time number of people entered, exited the region, or stayed in the region in the Monitoring module on the Control Client. Meanwhile, when an alarm is triggered in the region (such as people amount more/less than threshold), the client will notify the user by highlighting the region on the map.

15.4 View Remote Site Alarm

If you have added a remote site on a GIS map, you can view the information of alarms triggered on the remote site. Even if there is no alarm triggered at the current time, you can also view history alarms of the site.

Before You Start

Make sure you have added a remote site on the GIS map. See *User Manual of HikCentral Professional Web Client* for details.

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow All Modules \rightarrow Surveillance \rightarrow Monitoring$.
- 2. Optional: Select an area on the left to show its GIS map.
- **3.** Click the site icon to open the site details page.

iNote

If there are unhandled alarms triggered in the remote site, the number of unhandled alarms will be displayed on the upper right of the site icon.




Figure 15-1 Site Details

The color of site icon will turn blue.

4. Click View Unhandled Alarm to open the Unhandled Alarm window.

Alarm information including alarm name, alarm priority, triggering time, alarm source, etc. is displayed.

5. Optional: Perform the following operation(s).

Filter Alarm by Priority	Click $\overline{\mathbb{Y}}$ on the Alarm Priority column to filter alarms by alarm priority.
Filter Alarm by Status	Click 🍸 on the Alarm Status column to filter alarms by alarm status.

15.5 Operate Map

After opening map, you can perform one or more operations of the followings, such as zooming in or out map, selecting resource(s) on map, adding label, printing map, displaying map in full screen mode, and so on. After opening map, you can perform one or more operations of the followings, such as zooming in or out map, adding label, displaying map in full screen mode, and so on.

Zoom in/Zoom out Map

Use the mouse wheel or click 🗐 or 🧧 to zoom in or zoom out on the map.

Filter

Click and select the resource type you want to show on the map.

Real-Time Display of Face Comparison/Access Control/Vehicle List

Click s and select the item(s) to display real-time related captured face picture, access event, and vehicle list on the map.

Select Resource(s) on Map

Click **I**, and drag on the map to select resource(s).

Drag the selected resource(s) to the display window for live view or playback.

Add Label

Click **E** to add a label with description to the map.

Capture

Click 📷 , and drag on the map to select an area. You can save this area as a picture to local PC.

Print Map

Click 🔚 to print the map.

Locate Resource on Map

Move the cursor to the resource in the device list, click **Locate on Map** to locate the resource on the map. The located resources can be displayed in the center of the map.

Or start live view or playback of a camera, move the mouse to the lower edge of the display window and click Note on the left to locate the resource on the map.

IINote

Only when the resource is added to the map, you can locate the resource on map.

Search Location

By the search bar on the top of the map, you can search locations on GIS map and hot spot/hot region on the e-map by entering keyword(s).

Chapter 16 Access Control and Elevator Control

The system supports access control and elevator control functions. Access control is a security technique that can be used to regulate who can get access to the specified doors and elevator control can be used to regulate who can get access to the specified floors by taking the elevator.

After setting the persons' permissions of accessing specified doors and floors by assigning access levels to access groups, the authorized persons can access specified doors and floors with credentials.

On the Control Client, the operator can check the real-time access events (access granted or access denied, and so on), view the live video of the access point's related cameras (such as camera mounted inside the elevator), control the door or floor's status (such as remaining the door locked or switching the floor to access forbidden status).

You can also search the access records and perform entry & exit counting on the Control Client to see who presents her/his credential on the card reader of the access point, whether he/she accesses successfully, who enters or exits this room, and how many people still stays in the room.

16.1 Control Door Status in Live View

You can view the live video of the door's related camera(s). During live view, you can control the door status and check the card swiping records in real time.

Steps

- In the upper-left corner of the Control Client, select
 → All Modules → Surveillance → Monitoring .
- **2.** Drag the door to the display window, or double-click the door name after selecting the display window.
 - If the door is related with camera(s), the live view of these cameras will show. If two cameras are related, the live video will be displayed in Picture-in-Picture mode.

INote

You can click the thumbnail to switch the position of the two cameras.



Figure 16-1 Picture-in-Picture Mode

• If the door is not related with any camera, the door status will show in the center of the display window.



Figure 16-2 Control Door Status

• The access records will appear below the live view window in real time when events occur.

IINote

For relating cameras with the door, refer to the User Manual of HikCentral Professional Web Client.

- 3. Switch the door status among Unlocked, Locked, Remain Unlocked, and Remain Locked.
 - For the door related with camera(s):

Click the status icon in the upper-right corner of the display window and select the status.

- For the door not related with any camera:

Click the status icon in the center of the display window.

🚡 / 🚡 : Unlock

When the door is locked, unlock the door and it will be opened. After the door open duration, the door will be closed and locked again automatically.

II Note

For setting the door's opening duration, refer to the User Manual of HikCentral Professional Web Client.

👌 / 🔒 : Lock

When the door is unlocked, lock the door and it will be closed. The person who has the access permission still can access the door with credentials.

🔣 / 🔃 : Remain Unlocked

The door will be unlocked (no matter closed or opened). All persons can access the door with no credentials required (free access).

🖪 / 🗔 : Remain Locked

The door will be closed and locked. No person can access the door even the person has authorized credentials, except the super users.

II Note

For setting the person's super user permission, refer to the User Manual of HikCentral Professional Web Client.

4. Optional: Perform further operations after starting the live view of the door.

Control Door	Click 🔣 on the top of the display area to switch the status of all doors in the
Status in a	current site to remain locked/remain unlocked.
Batch	Remain Locked: Lock all doors. This function is applicable for situations

- Remain Locked: Lock all doors. This function is applicable for situations such as preventing a thief in the building from running away. Click
 Remain Locked → All to lock all doors in the current site; click Remain Locked → Part and select one or more emergency operation group(s) to lock all doors in the selected group(s).
 - Remain Unlocked: Remain all doors unlocked. This function is used when an emergency happens and the persons need to leave as quickly as possible, such as in a fire escape. Click Remain Unlocked → All to set all doors in the current site to remain unlocked; click Remain Unlocked → Part and select one or more emergency operation group(s) to set all doors in the group(s) to remain unlocked.
- Recover Status: Lock doors in the current site after the emergency. Click Recover Status → All to lock all doors in the current site; click Recover Status → Part and select one or more emergency operation group(s) to lock all doors in the group(s).

Control SingleClick in the upper-right corner of a door's live view window to switch theDoor Statusdoor's status to locked/unlocked/remain locked/remain unlocked.

Locate Door onClick is on the lower-left corner of the display window to show the mapMapand the door's location on the map.

Set TriggeringClick is to select a user-defined event. Refer to Manually Trigger User-EventDefined Eventfor details.

16.2 Control Floor Status in Live View

During live view, you can view the live video of the elevator's related cameras (such as cameras mounted inside the elevator). You can also control the status of the floors linked to the elevator.

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Monitoring .
- **2.** Drag the elevator to the display window, or double-click the elevator name after selecting the display window.

If the elevator is related with camera(s), the live view of these cameras will show. If two cameras are related, the live video will display in Picture-in-Picture mode. In Picture-in-Picture mode, click the thumbnail to switch the position of the two cameras.

INote

For relating cameras with elevator, refer to the User Manual of HikCentral Professional Web Client.

3. Click I in the upper-right corner of the display window to switch the floor status among **Temporary Access, Access with Credential, Free Access, Access Forbidden**.

Image: Temporary Access

During the temporary access time period, the persons can access this floor with no credentials required. After this time period, the floor will recover to Access with Credential status.

For details about setting the temporary access time period, refer to the User Manual of HikCentral Professional Web Client.

: Access with Credential

The person who has the access permission can access this floor with credentials.

🚥 : Free Access

All persons can access this floor with no credentials.

🐼 : Access Forbidden

No person can access this floor even if the person has the authorized credentials, except the super users.

INote

For setting person's super user privilege, refer to User Manual of HikCentral Professional Web Client.

Floor0.139 强	Floor	0.139 🖫	Floor0.139 📳	Floor0.	139 🖽
Floor0.139 强	Floor	0.139 强	Floor0.139 强	Floor0.139	
Floor0.139 强	Floor		Control: Temporary / Control: Access With		9 🖽
Floor0.139 强	Floor	-	Control: Free Access	Creden	9 🔃
Floor0.139 强	Floor	限 Floor	Control: Access Forb	idden	9 🖽
Floor0.139 强	Floor	0.139 强	Floor0.139 强	Floor0.	139 强
Floor0.139 强	Floor	0.139 强	Floor0.139 🔃	Floor0.	139 🖽
Floor0.139 强	Floor	0.139 强	Floor0.139 🖽	Floor0.	139 🖽

Figure 16-3 Control Floor Status in Live View

4. Optional: Perform further operations after starting the live view of the floor.

Control Floor Click 📰 on the top of the display area to switch status of all floors in the current site into access forbidden/free access.

Access Forbidden:

Status in a

Batch

This function is applicable for situations such as preventing a theft in the building from running away. Click Access Forbidden → All to set all floors in the current site as access forbidden; click Access Forbidden > **Part** and select one or more emergency operation group(s) to set all floors in the group(s) as access forbidden.

Free Access:

This function is used when emergency happens and the persons need to access all the floors. Click Free Access \rightarrow All to set all floors in the current site as free access; click **Free Access** \rightarrow **Part** and select one or more emergency operation group(s) to set all floors in the group(s) as free access.

Recover Status:

Recover floor status to access with credential after the emergency. Click **Recover Status** → All to set all floors in the current site as access with credential; click Recover Status → Part and select one or more

emergency operation group(s) to set all floors in the group(s) as access with credential.

Control Single Floor Status	Click 🔜 in the upper-right corner of a floor's live view window to switch the its status to free access/access with credential/access forbidden/ temporary access.
Locate Elevator on Map	Click 📓 on the lower-left corner of the display window to show the map and the elevator's location on the map.
Set Triggering Event	Click 💽 to select a user-defined event. Refer to <u>Manually Trigger User-</u> <u>Defined Event</u> for details.

16.3 Search Access Records

You can search for persons' access records triggered on specified access points (including doors and elevators) via the Client by setting search conditions. For example, if you select specific access points and set the event type to access denied by card, you can get all access denied events (accessing by swiping a card) triggered on the access points.

Before You Start

Make sure you have configured the access point event on the Web Client. For details, refer to the User Manual of HikCentral Professional Web Client.

Steps

- In the upper-left corner of the Control Client, select

 → All Modules → Investigation → Access
 Control Retrieval.
- 2. Select 🔤 Access Record Retrieval on the left.
- 3. Optional: Import access records to the system.
 - Import access records from the device(s).
 - a. Click **Import Event** \rightarrow **Import from Device** to enter the Import from Device page.
 - b. Select the device(s) from the device list.
 - c. Optional: Switch on **Specified Time Range** and set the start time and end time to import access records generated in the specified time period.

iNote

- If the device has uploaded access record(s) to the system before, switching on Specified Time Range is not required and access records during the past 7 days of the selected device(s) will be imported by default if no time range is specified.
- If the device has never uploaded any access record to the system before, you must switch on **Specified Time Range** for importing access records from the selected device(s).

d. Click **OK** to start importing.

A window will pop up to display the importing progress and the failure details.

- Import access records from the file which is exported from the device.

- a. Click **Import Event** \rightarrow **Import from File** to enter the Import from File page.
- b. Click 🗁 to select the file to be imported.

i Note

Only the encrypted file can be imported.

- c. Enter the password in the **Password** field.
- d. Click OK.

4. In the **Time** drop-down list, select the time during which the access records are generated.

IINote

- You can select **Custom Time Interval** to set a precise start time and end time.
- The time here can be the device time or the client time, which is based on the time zone settings in **System → General**.
- 5. Optional: In the Access Point area, click 📑 and select door(s) and elevator(s) from the resource list.
- 6. Optional: In the Record Type area, click [] to select record type(s).
- **7.** In the **Access Result** drop-down list, select an access result type to quickly filter access granted records or access denied records.
- 8. Set the searching mode.
 - a. Select **Person/Visitor** as the searching mode.
 - b. Select All, Person, or Visitor as the person type.
 - c. Select **Select Persons** or **Fuzzy Matching** as the searching mode.

Select Persons

Select persons in the person list.

Fuzzy Matching

Enter a keyword to search for persons whose name contains the keyword.

- d. Click **Add** to select the person(s), or enter the keywords of the person name for fuzzy matching.
- a. Select Card No. as the searching mode.
 - b. Enter the card number.

9. Optional: Switch on Skin-Surface Temperature Status and select Normal or Abnormal.

10. Optional: Switch on Wearing Mask or Not and select Wearing Mask or No Mask.

11. Click Search.

Matched access records are listed on the right.

12. Optional: Perform the following operations after searching for access records.

View Record Click the person name in the Full Name column to view the record details, Details Such as the recorded video or captured picture of the related camera (if configured), person information, and access information. If the person is a visitor, you can view the detailed visitor information and host information, including name, person profile, visit reason, belongings picture (if any), etc.

Filter Search Results by Person Type	Click 🝸 next to the column name Person/Visitor and select Person or Visitor to filter the search results.
Forgive Anti- Passback Violation	When a person attempts to use a card without following the anti- passback rule, the access will be denied. This is called "Anti-Passback Violation". When the anti-passback violation occurs, no access is allowed unless the anti-passback violation event is forgiven. You can click Forgive Anti-Passback on the top to forgive all the anti- passback violation events in the search results.
Export Single Record	Click 📑 in the Operation column to save a record as an Excel file in your PC, including the event details, the person information, person profile, recorded video file (if configured), etc.
	Note You can view the task progress in the Download Center.
Export All Searched Records	Click Export in the upper-right corner to save the searched access record details (including person name, person ID, event time, access result, etc.) in your PC as an Excel or a CSV file. If you select Excel , you can check Export Picture to save the captured pictures as well.
	Note
	 Up to 500 records can be exported each time. You can view the task progress in the Download Center.




Figure 16-4 Real-Time Events

16.4 Search Data Recorded on Device

Data recorded on devices are records (e.g., triggered events/alarms, card-swiping records, etc.) stored in access control devices, elevator control devices, and video intercom devices. The records can be events/alarms triggered by human behaviors detected by devices and those triggered by devices (such as device faults). You can search for the records in different dimensions according to your needs.

Steps

- 2. Click Device Recorded Data Retrieval on the left.
- **3.** In the Time drop-down list, select a time range for searching.



You can select **Custom Time Interval** to set a precise start time and end time.

4. Switch on the resource types where you want to search for records.

Access Point(s)

Access points include doors of access control devices and video intercom devices, and floors of elevator control devices. The records can be access records, operation records, and alarms triggered by human behaviors.

Device

Devices include access control devices, elevator control devices, and video intercom devices. The data recorded in these devices covers all events triggered by devices (such as device faults).

Alarm Input

The alarm inputs included in devices. The records are arming status changes.

5. Select the record source(s) and record type(s).

6. Click Search.

Device Recorded Data Retrieval								() toport
		burn 1	Area 2	Source Type	Access Control Device 1	Record Type	Time 1	Operation
Tever				August Connector		ATT AVE THE S.	321-0e-17-5.	G
trin				Arrest General D.		Same Alarval -	817-14-17 5.	e.
Access Point(a)	0.0			Arian California		INTY AUX TYPE L.	1027-04-07-0-	19
Device	•			Acces Control D.		1079 Auro Toro S.	100-04-010	9
linese ;	.0,			Avenue (Lener 1).		APR Auto Time 5-	311-04-17.8.	e.
				Autom Darweit (*		Revision Lington	397-24-178-	19
	- 5			August Darweit D.		arts ages from 5.	10.04.07.1	œ
R				Antes Consider.		Spranty Series	311-08-17.8.	2
A				Avera Datest P.		WERAM TIMES	321-24-111	Ð
				Access Control (1).		APP Auto Tria L.	1011-04-07-0	9
Record Type	38			Andrea Control 2		NT AUTO THE S.	311-04-173-	12
Ruses Central Single Arrest	R1			Arran Centeri P.,		with Auto Tena S	mp.04371.	Ð
Numer Control Tracks Among Failed				Accession 1.		APP Ages Total L.	1011-04-07-0-	œ
fullies followed instances Detector fungilies				Annal Control (C.		WP ANT THE ST	301-04-073.	13
Active Initiated Induzion Detector Recovered				Acres Colora (L.		AUX Aux Tree S.	MP1-04-37-9-	œ.
AC Press Direct				Accession of Low Street		any App from L.	1017-04-17-1.	0
Electro Taxant	1.08			southerst.		WE AND THE S.	201-04-0731	13
Search		100 +						

Figure 16-5 Device Recorded Data Retrieval

7. Optional: Perform further operations on the searched records.

Export Single Record	Click 📑 in the Operation column to save the record to the local PC as a CSV file.
Export All Searched Records	Click Export to save all the searched records to the local PC as an Excel or a CSV file.

16.5 Open Door for Multi-Factor Authentication

In access control, multi-factor authentication is an authentication method in which the door will unlock only after multiple persons authenticate multiple credentials in turn. This method is mainly used for locations with high security requirements, such as bank vault. With the mutual supervision of the persons, multi-factor authentication provides higher security for the assets in these locations.

You can set multi-factor authentication rule on the Web Client. For details, refer to the User Manual of HikCentral Professional Web Client.

If you set the access mode as **Remotely Unlock After Granted**, when the persons in the access group authenticate at the door, a window will pop up on the Control Client as follows.




Figure 16-6 Pop-Up Window of Remote Request

Click **Answer** to answer the request and start two-way audio. If the door is related with a camera, you can view the live video of the related camera. You need to verify the identity of the persons before opening the door.




Figure 16-7 Remotely Open Door

Click **Open Door** and then the door will be unlocked.

16.6 Handle Opening Door Request from Video Access Control Terminal

Video access control terminal supports voice talk with the connected client. Person can press button on the device front panel to send an opening door request to the security personnel and the security personnel can talk with the person via Control Client, view the live video of the video access control terminal's camera, and unlock the door if the person's identity is confirmed. This function is mainly used when the person forgets to take her/his credentials or for visitors.

IINote

Before the Control Client receiving the remote request from video access control terminal, you should first add a **Calling Surveillance Center** alarm for this video access control terminal's access point in the Web Client. For details about adding alarms, refer to *User Manual of HikCentral Professional Web Client*.

After pressing the \S button on the device front panel, a window will pop up on the Control Client. You can view the live view of the video access control terminal's camera and perform the following operations.

- Answer Request: Click **Answer** to start voice talk with the person who starts this request.
- Ignore Request: Click Ignore to ignore this request and close this window.

- Open Door: During voice talk, click **Open Door** to allow the person to get in.
- End Call: Click End Call to end voice talk and close this window.

16.7 Perform Entry & Exit Counting

By grouping the doors (adding entry & exit counting group), the system provides counting functions based on the entry and exit records on these doors. With this function, you can check who enters/exits this region and how many persons still stay in this region. The function is applicable for certain emergency scene. For example, during a fire escape, all people are required to exit the region.

Before You Start

Make sure you have added entry & exit counting groups to group the doors in the Web Client. For details, refer to *User Manual of HikCentral Professional Web Client*.

Steps

IINote

Currently, the platform only supports searching persons with access records in the last 24 hours.

- In the top left corner of Control Client, select
 → All Modules → Investigation → Access
 Control Retrieval .
- 2. Select Entry & Exit Counting on the left.
- **3.** In the **Source** list, select an entry & exit counting group.
- 4. In the Entry & Exit Counting Type drop-down list, select the type of persons you want to search. All

All the entering and exiting access records in the last 24 hours will be listed.

People Stayed

Persons who are still staying in the region will be listed. The system filters the persons whose entering record is found but exiting record is not found.

People Exited

Persons who entered and exited the region afterward will be listed.

5. Click Search.

All matched access records will be listed, showing information such as person details, location of last access, etc.

6. Optional: Perform further operations after searching.

View Event Details	Click the person name in the Name column to view the record details, including the recorded video of the access point's related camera (if configured), person information, and access information.
Export Single Record	Click 🕞 in the Operation column to download the record, including the person information, person profile, phone number, location of last access, etc.

Export All Searched Records	Click Export in the upper-right corner to export the searched access control events details (including the person information, person profile, phone number, location of last access, etc.).
	III Note
	Up to 100,000 records can be exported each time.
Print Single Record	Click 🚍 in the Operation column to print the record.
Print All Searched Records	Click Print in the upper-right corner to print all the searched records.

Chapter 17 Video Intercom

The system supports video intercom functions. Video intercom is an audiovisual communication and security technique used in a building or a small collection of buildings. With microphones and video camera devices at both sides, it enables the intercommunication via video and audio signals.

After adding device and person to the system and configuring related parameters, the operator can check the real-time events and alarms, view the live video of the related cameras, control the door's status (such as remaining the door locked), call indoor station and answer call, etc.

17.1 Control Door Status in Live View

For video intercom device, you can view the live video of its door's related camera(s). During live view, you can control the door status if needed, and view the access events in real time.

Steps

- In the top left corner of Control Client, select → All Modules → Surveillance → Monitoring to enter the Monitoring page.
- 2. Click Live View on the top to enter the live view page.
- **3.** Drag the door to the display window, or double-click the door name after selecting the display window.

If the door is related with camera(s), the live view of these cameras will show. If two cameras are related, the live video will display in Picture-in-Picture mode, which means one is at the bottom left of the other one.

If the door hasn't been related with any camera, the door status will show in the display window.

The access record will overlap the display window in real time, if access event happens.

IINote

For relating cameras with door, refer to the User Manual of HikCentral Professional Web Client.

4. Optional: In Picture-in-Picture mode, click the smaller video view to switch the view position of the two cameras.




Figure 17-1 Picture-in-Picture Mode

5. Click the icons in the middle of the window or click in the upper right corner of the window to switch the door status among **Unlocked**, **Locked**, and **Remain Unlocked**.

Unlock

When the door is locked, unlock the door and it will be open. After the door open duration, the door will be closed and locked again automatically.

INote

For setting the door's open duration, refer to User Manual of HikCentral Professional Web Client.

Lock

When the door is unlocked, lock the door and it will be closed. The person who has the access permission can access the door with credentials.

Remain Unlocked

The door will be unlocked (no matter closed or open). All the persons can access the door with no credentials required (free access).

i Note

For setting person's super user privilege, refer to User Manual of HikCentral Professional Web Client.

6. Optional: Perform the follow operations after starting the live video of the door.

Control Door StatusClick I on the top of the display area to switch status of all doors in
the current site into remain locked/remain unlocked.

Place Door on Map

Click on the lower-left corner of the display window to show the map and the door's location on the map.

17.2 Call Indoor Station

If the person has been linked with an indoor station, you can call the added indoor station via the Control Client for starting voice talk with the resident, viewing the video of the indoor station's camera, etc.

IINote

Make sure you have added the person and linked the person with an indoor station via Web Client.

In the top left corner of Control Client, select $\square \rightarrow All Modules \rightarrow Tool \rightarrow Video Intercom$ to enter the video intercom page. Select a person group to filter the persons in the group or in its sub person groups (configurable), or select **Person Name** or **Indoor Station** and enter the keywords to filter the person or indoor station.

Click \mathbb{Q}_{-} on Operation column to start calling the indoor station.



Figure 17-2 Call Indoor Station

After the call is answered, you can talk with the person, view the video, or perform other operations as follows.

- Click 🚮 to adjust the volume of the speaker.
- Click a to end speaking.
- Click 🚺 to adjust the volume of the microphone.
- Click at to start recording the audio during video intercom and click to end recording. The recorded file will be saved in the default path in local PC, and you can click **Open Folder** in the pop-up window to view the file.

17.3 Answer Call

You can answer the call from the added door station and indoor station via the Control Client.

When the Control Client receives a call from the door station or indoor station, a window will pop up. You can click **Answer** to answer the call, or click **Refuse** to decline the call.




Figure 17-3 Answer Call

After the call is answered, you can perform the following operations.

- Click **Open Door** to open the linked door remotely.
- Click () to adjust the volume of the loudspeaker.
- Click 🎍 to adjust the volume of the microphone.
- Click at to start recording the audio during video intercom and click at to end recording. The recorded file will be saved in the default path in local PC, and you can click **Open Folder** in the pop-up window to view the file.
- Click End Call to end the call.

IINote

You can only answer one video intercom device's call via Control Client at the same time.

Chapter 18 Vehicle

The system supports managing ANPR (Automatic Number-Plate Recognition) cameras and UVSS (Under Vehicle Surveillance System). After adding ANPR cameras and UVSS in the system, the license plate number and undercarriage picture of the passing vehicles will be detected and captured. The system also provides entrance and exit management service and it can control the entry and exit of the detected vehicles according to the entry & exit rules you set. In addition, the system supports parking fee management, including adding coupons and selecting the payment method before opening the barrier gate.

On the Control Client, you can view the live video of the ANPR cameras and check the recognized license plate numbers of the detected vehicles. Also, for UVSS, you can check the real-time undercarriage image of this vehicle.

On the Entrance and Exit, you can view the information of the vehicles entering and exiting the parking lot. The system can open the barrier gate of the parking facility automatically according to the entry & exit rules. If the barrier doesn't open, you can also open it manually via the Control Client to allow the vehicle to enter or exit.

You can also view vehicle passing records and their detailed information, such as the passing time, entry pictures, exit pictures, parking information. And then you can manage a vehicle's parking fee by adding a coupon if needed. After payment, you can select a payment method to open the barrier gate for the vehicle.

18.1 View ANPR Camera's Live Video

Automatic number-plate recognition (ANPR) is a technology that uses optical character recognition on images to read vehicle registration plates. During live view of the ANPR cameras, the license plate numbers of the passing vehicles are recognized and displayed on the right side of the live view window. ANPR is becoming a significant component for recognizing stolen vehicles. Successfully recognized plates may be matched against databases (allowlists or blocklists including "wanted person", missing person, suspected terrorist, etc). You can mark the suspicious vehicle, add a new vehicle to the vehicle list, and search the passing vehicle information.

Before You Start

Add an ANPR camera to the system via the Web Client. For adding camera, refer to User Manual of HikCentral Professional Web Client.

Perform this task when you need to view ANPR camera's live video.

Steps

- In the top left corner of the Home page, select
 → All Modules → Surveillance → Monitoring .
- 2. Start the live view of an ANPR camera.

- Drag an ANPR camera from the resource list on the left to the display window to start live view.
- Double-click an ANPR camera name in the device list on the left to start live view.




Figure 18-1 Live View of ANPR Camera

- **3. Optional:** Perform the following operation(s) if needed.
 - Choice 1: Click at the bottom of the page, and then click **Vehicle Record** to enter the operation panel.
 - Choice 2: Click on the right of the page, and then click **Vehicle** to enter the operation panel.

Mark Vehicle	 If you think that a vehicle is suspicious, you can mark the vehicle. The marked vehicles can be filtered out later when searching for the related vehicle passing information in the Vehicle Search module. For Choice 1: Click in the Operation column to mark the vehicle. For Choice 2: Move you cursor to the target vehicle area, and then click in the vehicle.
Add Vehicle to Vehicle List	 If the Client recognizes a vehicle that is not added to the vehicle list, you can add it to the vehicle list manually. See <u>Add Recognized Vehicle to Vehicle List</u> for details. For Choice 1: Click to add the vehicle to a vehicle list. For Choice 2: Move you cursor to the target vehicle area, and then click to add the vehicle to a vehicle list.
Search Vehicle	If you want the know how many times the vehicle has entered and exited the parking lot, you can search for the passing record(s) of the vehicle. For details, refer to Search for Vehicle Passing Records .

	 For Choice 1: Click in to enter the Vehicle Passing Record Search page to search for the passing record(s) of the vehicle. For Choice 2: Move you cursor to the target vehicle area, and then click into enter the Vehicle Passing Record Search page to search for the passing record(s) of the vehicle.
Delete All Records	If you enter the operation panel via choice 1, you can click m to delete all the vehicle records.
Subscribe All Vehicle Events	If you enter the operation panel via Choice 1, you can check Subscribe All to subscribe all vehicle events.

18.2 View UVSS's Live Video

An under-vehicle surveillance system (UVSS) generally consists of imaging systems mounted on a roadway and used at facility access points, particularly at secure facilities. It is used to detect threats—such as bombs—that are hidden underneath vehicles. Cameras capture images of the undercarriage of the vehicle for manual or automated visual inspection by security personnel or systems. As the vehicle arrives at the checkpoint and drives over the imaging unit, the cameras capture images of the undercarriage and transmit them to Control Client. The undercarriage picture of the passing vehicle is captured and displayed on the live view window. The license plate number of the passing vehicle is recognized and displayed on the right side of the live view window.

Before You Start

Add a UVSS to the system via Web Client. Refer to User Manual of HikCentral Professional Web Client for details.

Perform this task when you need to view UVSS's live video.

Steps

- **2.** Start the live view of UVSS.
 - Drag the UVSS from the device list on the left to the display window to start live view.
 - Double-click the UVSS name in the device list on the left to start live view.



Figure 18-2 Live View of UVSS

You can view the live video of the UVSS linked camera, the undercarriage picture, and recognized license plate number of the passing vehicles.

- **3. Optional:** Mark important information on the undercarriage picture.
 - 1) Move your cursor onto the undercarriage picture.
 - 2) Click 💹 on the toolbar.
 - 3) Draw on the undercarriage picture to mark important information such as the explosive.
- **4. Optional:** Perform the following operation(s) if needed.
 - Choice 1: Click at the bottom of the page, and then click **Vehicle Record** to enter the operation panel.
 - Choice 2: Click on the right of the page, and then click **Vehicle** to enter the operation panel.

Mark Vehicle	If you think that a vehicle is suspicious, you can mark the vehicle. The marked vehicles can be filtered out later when searching for the related vehicle passing information in the Vehicle Search module.
	 For Choice 1: Click in the Operation column to mark the vehicle. For Choice 2: Move you cursor to the target vehicle area, and then click to mark the vehicle
Add Vehicle to Vehicle List	If the Client recognizes a vehicle that is not added to the vehicle list, you can add it to the vehicle list manually. See <u>Add Recognized Vehicle to Vehicle List</u> for details.
	 For Choice 1: Click to add the vehicle to a vehicle list. For Choice 2: Move you cursor to the target vehicle area, and then click to add the vehicle to a vehicle list.

Search Vehicle	If you want the know how many times the vehicle has entered and exited the parking lot, you can search for the passing record(s) of the vehicle. For details, refer to Search for Vehicle Passing Records .
	 For Choice 1: Click at to enter the Vehicle Passing Record Search page to search for the passing record(s) of the vehicle. For Choice 2: Move you cursor to the target vehicle area, and then click to enter the Vehicle Passing Record Search page to search for the passing record(s) of the vehicle.
Delete All Records	If you enter the operation panel via choice 1, you can click m to delete all the vehicle records.
Subscribe All Vehicle Events	If you enter the operation panel via Choice 1, you can check Subscribe All to subscribe all vehicle events.

18.3 Entrance & Exit Control

HikCentral Professional provides entrance & exit management service. You can set entry & exit rules for entrance and exit on the Web Client so that the barrier gates will be controlled by the platform according to the rules you set. On the Control Client, you can control the barrier gates both automatically and manually, view the detailed information of vehicles entering and exiting the parking lot, and hand over shifts.

On the Control Client, you can go to $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Parking Lot to perform these operations.

To manually control the barrier gates, you can click **Barrier Control** \rightarrow **Lock/Unlock All Barrier Gates** or click **Barrier Control** \rightarrow **Lock/Unlock** to lock or unlock all barrier gates in the parking lot according to actual needs. You can click **Barrier Control** \rightarrow **Open/Close/Remain Open** in the lower left corner to manually control a barrier gate. In the upper-right area of the page, the number of vacant parking spaces is displayed, and you can click it to display the real-time number of vacant parking spaces. This number can help you better decide whether to allow a vehicle to enter.

To view the detailed information of the vehicles detected at the lane, you can click **Vehicle Record** in the lower left corner of the page, and all the records will be displayed. You can click a specific record to view more details, such as the captured pictures and parking information of the vehicle.

								Showitz.	
	Value Paters	Lines Pale .	- Service Line	Intering or Eating	Passing Time	Here to	-	Operation	
圖									
Webble Burnet	44								6)
55	14								a)

Figure 18-3 Entrance & Exit Control

18.3.1 View Passing Vehicle Information

On the Entrance and Exit page, you can view information of vehicles (including visitors' vehicles) entered or exited from the parking lot including captured vehicle pictures, license plate numbers, vehicle lists, vehicle directions, passing time, allowed or not, etc. You can also view detailed information of the passed vehicles, mark suspicious vehicles, add passed vehicles to a vehicle list, etc.

In the top left corner of the Home page, select $\square \rightarrow All Modules \rightarrow Surveillance \rightarrow Parking Lot \rightarrow$ **Entrance and Exit**, and select an entrance/exit in the drop-down list in the upper-left corner of the page.

View Real-Time Passing Vehicle Information

After entering the Entrance and Exit page, the video and picture of the vehicle captured by the lane's related camera are displayed. You can hover the cursor on the picture and click > or < to switch pictures. Click to view the entering video.




Figure 18-4 Vehicle Entering

In the **Exit** area, the picture and video of the vehicle exiting the parking lot are displayed, and the corresponding picture captured when it was entering the parking lot is displayed in the **Enter** area with related information. Click **Exit** to view the exiting video. If the corresponding entering picture cannot be found, click **Fuzzy Matching** to open the Matching Result window to select a vehicle in the entering pictures which are regarded as entering pictures of similar vehicles to this vehicle. After that, the selected picture will be displayed under the **Fuzzy Matching** button as the entering picture of the vehicle.




Figure 18-5 Vehicle Exiting




Figure 18-6 Matching Result

View History Passing Vehicle Information

Click **Vehicle Record** to show the passed vehicles and their information. You can perform the following operations if needed:

• View Vehicle Passing Details

Click **t** to view vehicle details (including owner information, vehicle features, etc.) and entering record including lane, direction, entering time, etc. You can also allow the vehicle to enter or exit from the parking lot, view video of the vehicle, and correct the license plate number on this page.

IINote

If a vehicle owner is a visitor, the vehicle owner name will be displayed in blue color. Click the vehicle owner name to show visitor information (including host, visiting validity period, ID type, ID No., phone number, gender, and visitor group).

Mark Vehicle

If you think a vehicle is suspicious, click it to mark the vehicle. The marked vehicles can be filtered out later when searching the related vehicle passing information in Vehicle Search module.

Add Vehicle to Vehicle List

If the Client recognizes a vehicle that is not added to the vehicle list, you can add it to the vehicle list manually. Click **a** to add the vehicle to a vehicle list. See **Add Recognized Vehicle to Vehicle List** for details.

• Search Vehicle

Click **m** to enter the Vehicle Search page to search the related vehicle passing information. For details, refer to **Search for Vehicle Passing Records**.




Figure 18-7 View History Passing Vehicle Information

You can also allow vehicles to enter/exit, correct license plate number, and control barriers manually on this page. See <u>Manually Open Barrier for Vehicles</u>, <u>Correct License Plate Number</u>, and <u>Manually Control Barrier</u> for details.

18.3.2 Automatically Open Barrier for Vehicles

The vehicle can enter or exit the parking lot with the barrier gate opened automatically in the following situations:

Barrier Opened Automatically According to Entry & Exit Rule

If you have set the entry & exit rule for the vehicles in the vehicle list or not, and set **Opening Barrier for Entering** or **Opening Barrier for Exiting** as **Automatic**, and the time is within the authorized time period, when the system detects a vehicle at the lane, the barrier gate will be opened automatically.

You can view the details of the vehicle such as license plate number, vehicle brand, color, entering/ exiting time on the Control Client.

IINote

For details about setting the entry & exit rule, refer to the User Manual of HikCentral Professional Web Client.




Figure 18-8 Example: Barrier Opened Automatically for Vehicle in Vehicle List

Barrier Opened Automatically After Swiping Card

If you have linked one access control device or video intercom device with the lane, the owner of the vehicle in the vehicle list can also swipe her/his card on this device to verify her/his identity when entering or exiting the parking lot.

The system will find out the vehicle information linked with this card and judge whether to open the barrier gate automatically according to the entry & exit rule of its vehicle list. If you have set **Opening Barrier for Entering** or **Opening Barrier for Exiting** as **Automatic**, and the time is within the authorized time period, the barrier gate will be opened automatically. In this situation, you can use access control device or video intercom device instead of ANPR camera at the entrance and exit to check whether the card is linked with the vehicle in the vehicle list.

IINote

- Before enabling this function, you need to click **Swipe Card** in the upper right area, and select an entrance or exit to enable card swiping for the barrier gate there.
- Make sure you have already linked cards with the vehicles when adding vehicles and setting vehicle owner information on the Web Client.
- Make sure you have already linked an access control device or video intercom device with the lane on the Web Client.
- For details about the above settings on the Web Client, refer to the User Manual of HikCentral Professional Web Client.




Figure 18-9 Swipe Card to Open Barrier

18.3.3 Manually Open Barrier for Vehicles

On the Control Client, the information of the detected vehicles at the lanes will be displayed. If the barrier gate is not opened by the system automatically, you can open it manually via the Control Client.

In the top left corner of the Home page, select $\square \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Parking Lot \rightarrow **Formula** Formation and Exit to open the barrier gate manually in the following situations:

One-Touch Open Barrier Gate

Click **Allow** button on the Enter or Exit panel to open the barrier gate at the entrance or exit lane. You can also press the shortcut key on the keyboard to open the barrier gate.

IINote

You can set the shortcut keys for opening barrier gate in System \rightarrow Video \rightarrow Shortcut .



Figure 18-10 One-Touch Opening Barrier Gate

Open Barrier Gate and Enter Remarks for Entry

For the vehicles at the entrance lane, you can also set the remark information if needed. For example, you can enter why you allow this vehicle to enter the parking lot even though it is not in any vehicle list.

In the Enter panel, click **Allow** \rightarrow **Advanced** to enter the remark information.




Figure 18-11 Advanced Opening Barrier Gate

In the pop-up **Advanced** window, you can also select a vehicle list which has enabled with **Parking Space Control** function, which means this vehicle will occupy one parking space of this vehicle list. For example, if the parking lot is shared by three companies (company A, B, and C), when a visitor of company C wants to park in the parking lot, the security guard can open the barrier manually after verifying her/his identity and select the vehicle list of company C.

IINote

For details about setting **Parking Space Control** function of vehicle list, refer to the User Manual of HikCentral Professional Web Client.

Open Barrier During Video Intercom

If you have linked one access control device or video intercom device with the lane, the owner of the vehicle can press \S button on the device front panel to send an opening barrier request to the security personnel and the security personnel can talk with the person via Control Client, view the live video of the device's camera and capture unit (if any), and open the barrier if the person's identity is confirmed.

IINote

Before the Control Client receives the remote request from the device, you should first add a **Call Center** alarm for the parking lot on the Web Client. For details about adding alarms, refer to *User Manual of HikCentral Professional Web Client*.



Figure 18-12 Start Video Intercom to Send Opening Barrier Request

After pressing the \S_{a} button on the device front panel, a window will pop up on the Control Client as follows:

Access Request			×
	Calling	Entrança Time Vehicle List Lane Entrança fir Ditt Vehicle Type Brand Color Owner's Telephone	12/12 09:12:23 The East Gate 001 The East Gate Entrance & Exit
(1/4)			Answer

Figure 18-13 Access Request Received by Control Client

You can click **Answer** to view the live view of the device's camera as well as the capture unit and start voice talk with the person who starts this request. You can also click **Ignore** to ignore this request and close this window.



Figure 18-14 Video Intercom

During voice talk, click **Allow** to open the barrier gate.

You can also click **Advanced** to enter the remark information if needed, and select a vehicle list which has enabled with **Parking Space Control** function, which means this vehicle will occupy one parking space of this vehicle list.

For example, if the parking lot is shared by three companies (company A, B, and C), when a visitor of company C wants to park in the parking lot, the security guard can open the barrier manually after verifying her/his identity and select the vehicle list of company C.

iNote

For details about setting **Parking Space Control** function of vehicle list, refer to the User Manual of HikCentral Professional Web Client.

Click **End Call** to end voice talk and close this window.

18.3.4 Correct License Plate Number

You can correct the license plate numbers recognized by capture units.

You can correct the license plate number of vehicles entering or exiting the parking lot. Click in to edit the recognized license plate number.




Figure 18-15 Entrance/Exit Page

18.3.5 Manually Control Barrier

This function is applicable for diverse situations. For example, during rush hour, controlling barrier by a capture unit or card-swiping is very time-consuming. In this circumstance, the guard can open/close the barrier manually or set the barrier status as remaining open so that vehicles are able to pass quickly to save time. Meanwhile, if a capture unit failed to recognize a vehicle in the vehicle list, or one failed to open the barrier by swiping card, the guard can also open/close the barrier manually to allow the vehicle to pass.

In the top left corner of the Home page, select $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Parking Lot \rightarrow **Entrance and Exit** to enter the Entrance and Exit page, and click Barrier Control in the lower left area of the page.

Click **Open** to open the barrier for one time; click **Close** to close the barrier; click **Remain Open** to make the barrier gate remain open.

Click Lock to lock all the barrier gates, and click Unlock to unlock all the barrier gates.

Click **Capture** to capture the picture of the vehicle passing through the barrier gate.




Figure 18-16 Manually Control Barrier

18.3.6 Hand Over Shifts

On the Control Client, you can hand over shifts to other operators (i.e., the persons responsible for payment management). Before handover, you need to check the information about the payment you have managed. Besides, you can print the payment information if needed.

Steps

- 1. In the top left corner of the Home page, select
 → All Modules → Surveillance → Parking Lot
 → F Latrance and Exit to enter the Entrance and Exit page.
- 2. In the upper right area, click Shift Handover.

The Payment Overview window will pop up.

£ 0.00		
Cash		
€ 0.00		
Account Deduction	1	
€ 0.00		
Discount Amount		
€ 0.00		
Discount Details		
Discount Rule	Times	

Figure 18-17 Payment Overview Window

- **3.** Check the payment information.
- 4. Optional: Click Print to print the payment information.
- 5. Click OK.

The current account will be logged out.

18.4 Parking Space Monitoring

On the Parking Space Overview page, you can view the statistics of parking spaces, and can search for specific statistics by parking space No., license plate number, and parking time.

The Parking Space Overview page displays various kinds of statistics of parking spaces, including the occupancy rate of the parking spaces in a parking lot, the number of vacant parking spaces, occupied parking spaces, and parking spaces with unknown status, and the number of overtime parking and parking violations.



Figure 18-18 Parking Space Overview

You can click a floor name to view the statistics of the parking spaces of this floor. On the following page, you can move to a specific parking space to view its detailed information, and can click a parking space to view its real-time status and search for parking records. Moreover, you can click **Occupancy Status Overview** or **Parking Duration Overview** to view these two types of statistics respectively.




Figure 18-19 Floor Parking Space Overview

18.5 Add Recognized Vehicle to Vehicle List

Recognized vehicle license plate number will be displayed both on the live view page and the Entrance/Exit page. So you can add the recognized vehicles to vehicle list on the two pages. Besides, you can add a recognized vehicles to vehicle list on the Vehicle Search page.

Add Recognized Vehicle to Vehicle List on Live View Page

Select a camera for license plate recognition to start live view. Click at the bottom of the client to show the event list, and then click **Vehicle Record** tab to show vehicle recognition events.



Figure 18-20 Recognized Vehicles

At the bottom of the page, click $\boxtimes \rightarrow$ **Vehicle Record** $\rightarrow \boxtimes$ to open the Add to Vehicle List panel; on the right of the page, click $\boxtimes \rightarrow$ **Vehicle**, hover the cursor on a target vehicle area, and click \boxtimes to open the Add to Vehicle List panel.

Set the vehicle information including license plate number, validity, vehicle features, vehicle owner information, and select a vehicle list to add the vehicle to. Click **Add** to add the vehicle to the selected vehicle list.

Add to Vehicle List	
* License Plate Number	
*Vehicle List	
Reality	
Repaired Streets	
Validity	
Validity	
Last Name	
Validity Last Name First Name	
Last Name	

Figure 18-21 Add to Vehicle List

IINote

See *Live View* for details about starting live view.

Add Recognized Vehicle to Vehicle List on Entrance and Exit Page

Enter the Entrance and Exit page, the recognized vehicles will be displayed in the **Vehicle Record** tab page.




Figure 18-22 Vehicle Record

Click **E** in the Operation column to open the Add to Vehicle List panel.

Set the vehicle information including license plate number, validity, vehicle features, vehicle owner information, and select a vehicle list to add the vehicle to. Click **Add** to add the vehicle to the selected vehicle list.

Add Recognized Vehicle to Vehicle List on Vehicle Search Page

Search vehicles recognized by entrance and exit. See <u>Search for Vehicle Passing Records</u> for details. In the search results area, click $[]_+$ in the **Operation** column to open the Add to Vehicle List panel.

Mark 1	Scena Pale Number	TrieCorest Chert)	Camera Name Overal Plac. Vehicle Lid	Country/Region :	Vehicle Type :	Band 2	Caller	Dealtin 1	Operat	-
10		And States of Street,	Firmer B	-	14	1004	-	-	12	0
		-	Prove 8	-	10	-	-	-	13	0
			Alasta B	conclusion.	10	10.0		-	0	(3
17		And other states.	Warman B.	International Property lies:	14	104	-	-	.0	3
			Statut &	institute.	10	100	-	-	12	13
n.		And in case of the second	Warter B	rest ingen	14	100		-	12.	4
1		101103-011-0408	Contract B	course by pro-	10.	1000	-	-	0	0
		-	Summer B	restrain.	100	100	-	-	0	15
p=			Warner 10	Trained Streamber	1.0		-	(inc.)	0	13

Figure 18-23 Vehicle Search Results

Set the vehicle information including license plate number, validity, vehicle features, vehicle owner information, and select a vehicle list to add the vehicle to. Click **Add** to add the vehicle to the selected vehicle list.

18.6 Vehicle and Record Search

In the Vehicle Search module, you can search for various types of records, including the vehicle passing records, parking records, payment records, etc. Each record is attached with highly detailed information related to it, which can give the vehicle owner and the administrator a whole picture

of the vehicle's activity in a parking lot. Therefore, these records can help you to manage vehicles and parking lots much better.

18.6.1 Search for Vehicle Passing Records

If the added Automatic Number-Plate Recognition (ANPR) camera, Under Vehicle Surveillance System (UVSS), and entrance and exit are properly configured, and the vehicle license plate number is recognized by the cameras or capture units linked to the entrance and exit, you can search the related vehicle passing information.

Steps

INote

Make sure your license supports ANPR function. Otherwise, ANPR function cannot perform normally in the system.

1. In the top left corner of the Client, select
 → All Functions → Investigation → Vehicle Search
 → Passing Vehicle Search .

2. Set a time range.

- Select to search the vehicle passing records generated today, yesterday, current week, last 7 days, or last 30 days.
- Click **Custom Time Interval** to set the search time range.
- 3. Select Camera, UVSS or Entrance and Exit as the source of passing vehicle records.

The camera, UVSS, or entrance/exit will be automatically displayed under the Source.

INote

For camera, you can click 📭 , select the current site or a Remote Site from the drop-down list and select the ANPR camera(s).

4. Set searching conditions according to your needs.

Marking Status

Search marked or unmarked vehicles' passing records.

Country/Region

Select the country/region where the vehicle's license plate number is registered.

License Plate Number

Select **No License Plate** to search vehicles without license plate number; select **With License Plate** and enter a vehicle's license plate number or key word of license plate number.

Vehicle Owner

Enter the vehicle owner's name or keyword of name.

Vehicle Type

Select the type of the vehicle from the drop-down list.

Brand

Select the brand of the vehicle from the drop-down list.

Color

Select the color of the vehicle from the presented colors.

Driving Direction

- Forward: the vehicle moved toward the camera with its headstock facing the camera.
- **Reverse**: the vehicle moved away from the camera with its rear facing the camera.
- **Other**: the vehicle moved toward or away the camera in other directions.

Driving Speed

Set a range of driving speed.

Vehicle List

Search vehicle passing records of vehicles in certain vehicle list(s).

Custom Information

The custom items of vehicle information you added.

5. Click Search.

The vehicle passing records that match the search conditions will be displayed in the right area.

IINote

You can click \equiv or \boxplus to switch between List Mode and Thumbnail Mode.

6. Optional: Perform the following operations if needed.

Mark Vehicle	Click 📄 to mark the vehicle. The marked vehicles can be filtered when searching the related vehicle passing information recorded by the camera or UVSS.
Add to List	If the vehicle is not added to the vehicle list, you can add the new vehicle to the vehicle list manually. Click 📑 to add the vehicle. See <u>Add Recognized</u> <u>Vehicle to Vehicle List</u> for details.
View Picture	Click a vehicle's license plate number and click Picture tab to view the captured vehicle picture or undercarriage picture.
View Video	Click the Plate Number column and click Record to view the linked video file of the passing vehicle.
	Note
	 When viewing the video file of passing vehicles, you can control the playback.
	 Click Go to Monitoring to switch to Monitoring page. Click is to export the video file to the local PC.
Download Single Vehicle Passing Record	Select a vehicle and click 🗈 to save the vehicle's information (CSV file), vehicle passing picture, and recorded file in your PC. The vehicle passing

	picture and recorded file will be saved in the same folder as the CSV file. For details about downloading, refer to <u>Manage Downloading Tasks</u> .
View Vehicle Information	Click a license plate number in the list to view the detailed information of the vehicle.
Sort Records	Click Sort by Time or Sort by Vehicle Passing Times in the upper-right corner to sort vehicle passing records.
	Sort by Time
	Sort records by the time vehicles passed through the entrance & exit.
	Sort by Vehicle Passing Times
	Sort records by the number of times vehicles passed through the entrance & exit.
Export Vehicle Passing Records	 a. Click Export in the upper-right corner to open the Export panel. b. Select Excel, CSV, or PDF as the format of the exported file. Check Export Picture to save vehicles' pictures in your PC with the Excel file. c. Click Browse to select a saving path. d. Click Save.
	i Note
	 Up to 500 vehicle passing records with captured pictures can be exported at one time. Up to 100,000 vehicle passing records without captured pictures can be exported at one time.
Edit Vehicle Information	On a certain vehicle's page, click Edit to modify the recognized license plate number as needed.

18.6.2 Search for Payment Records

If a vehicle pays the parking fee and exits the parking lot, its payment information, such as the payment source and operation time, will be recorded in the platform. On the platform, you can search for the payment records generated in a specific parking lot or the records of a specific vehicle by setting search conditions according to actual needs. You can also export the records to your PC. With the statistics, you can monitor some of the transactions done in the parking lots, which can help you to manage the parking lots better.

Steps

In the top left corner of the Control Client, select → All Modules → Investigation → Vehicle
 Search → Payment Record Search .

Payment Record Search											13.1	Esperi
Time		Plane Tex.	Genthumber	Which Type	Faction Lot.	Antering To-	Rating Involve	Pages-	ь.	$p_{0,\cdot}$	Pc.	14-
Lan Britan	+											
Plane No.				-		-	1100		۰.	~	7	
Card Number												
Vehicle Type												
Parking Sof		÷.										
		1										
Entrance & Salt												
Operatur												
46 -	4.											
Payment Method												
Mi Cash Minish Danis.												
Payment Source												
M Burn Cirela												
- And -		1	+									

Figure 18-25 Payment Record Search Page

- 2. Set search conditions according to actual needs.
 - 1) Set a time range.

IINote

You can select today, yesterday, current week, last 7 days, or last 30 days from the drop-down list to search for the records generated in a relevant period, or click **Custom Time Interval** to set a time range by yourself.

- 2) **Optional:** Enter the license plate number of the vehicle.
- 3) **Optional:** Enter the card number of the vehicle.
- 4) Select the type of the vehicle or **All** from the drop-down list.
- 5) Select a parking lot or **All** from the drop-down list.
- 6) Select an operator (the person responsible for collecting the fee) or **All** from the drop-down list.
- 7) Select the payment method from All, Cash, and Vehicle Owner Account.
- 8) Select the source of payment from All, Booth, and Toll Center.
- 3. Click Search.

The matched record(s) will be displayed in the right area.

4. Optional: In the upper-right corner, click **Export** to export the record(s) to your PC.

18.6.3 Search for Parked Vehicles

If the actual number of vacant parking spaces is different from the number displayed on the guidance screens, you can search for the vehicles that already exited but still recorded in the parking lot to edit the vehicle information. For example, for parking lots requiring all on-site

vehicles out at the end of a day, you can search for the vehicles that are still in the parking lot and export the vehicles' information. In another situation, if a vehicle is manually allowed to exit the parking lot, the number of vacant parking spaces may not be updated in time. In this situation, you can search for the vehicle and delete it from the vehicle list of the parking lot to update the number of vacant parking spaces.

Steps

- 1. In the top left corner of the Client, select
 → All Functions → Investigation → Vehicle Search
 → Parked Vehicle Search .
- 2. Set searching conditions according to actual needs.

- 4	346. 1	No. 1	184.1											
- 4				Dec 1	Concili-	101.1	104.1	De. 1	34.1	(10.1)	16.7	18. T	14.1	Tane 1
		100		land.	patient.	Arian.	-		-		Ref (s.	he.	pane .	. Deci
			1014	hand.	Datas.	-	-	10414	100.00	in the	Barba.	Sector.	Apres .	ania.
- 08		-	and the	tind.	Interio.	A.1.0	terrain.				No. Inc.	14	lary.	Part.
0.00	-	20			-	1	1			-		100	-	in the second
0.00														
0.088				100	10000	-	100.0				14.04			
128		-	3214.	-		Apres	100.7-				Patrone	10mm	100	00046
1.08	-	**	1911-6.	(minute	-	Autom.	for p.		-		1140	Server.	104	744
(39)		-	2214.	-	++++++	4,010	$l = p_{\rm c}$		1000		7424	total.	Aprent.	-
. CBI	-	-	-	2 Marca	inene.	Adda.	Inc.		-		iner-	later.	ine	their
0.00			3074	210000	-	A.01	THE P.		-		Patrice	Ser	104	Date:
108	-	-	1014	interes.		A	1007		-		Tella.	track.	1000	-
0.00		-	-	Inter		-	1-1-		-		-	later -	100	Per .
	-	-	3014	25744		-	Fair (Par		-		Sec.	age b.	ines.	-
		-	ani.	-			100.0		-		the bar.	Inter.	Une	Sec.
	-	-	1000.00	(infrare)		A	timp.		-		desc (au)	Tet.	100	Parts .
		-	2014	(interior)		Addr.	field.		-		Autors	had	itter	Tailog .
	-		-	1000		1000	1000		-		1400	late:	10.00	Set .
		-		-					+			8-1	-	
				33 40 30 30 33 40 40 30 40 33 40 40 30 40 33 40 40 30 40 33 40 40 30 40 33 40 40 30 40 33 40 40 30 40 33 40 40 30 40 33 40 40 30 40 34 40 40 30 40 35 40 40 30 40 36 40 40 30 40 36 40 30 40 30 40 36 40 30 40 30 40 36 40 30 40 30 40 36 40 30 40 30 40 37 40 30 <td< td=""><td>Image: state Image: state Image: state Image: state Image: state Image: state Image: state Image: state Image: state Image: state Image: state Image: state Image</td><td>13 11 1212, 10, 10, 10, 10, 10, 10, 10, 10, 10, 10</td><td>13 14 13 13 13 14 14 14 14 13 13 11 13 13 13 14 13 14<!--</td--><td>10 10<</td><td>100 100<td>100 100 300 h Mark <thm< td=""><td>100 100<td>100 100<td>100 100 200 h 100 h 100</td><td>100 100</td></td></td></thm<></td></td></td></td<>	Image: state Image: state Image: state Image: state Image: state Image: state Image: state Image: state Image: state Image: state Image: state Image: state Image	13 11 1212, 10, 10, 10, 10, 10, 10, 10, 10, 10, 10	13 14 13 13 13 14 14 14 14 13 13 11 13 13 13 14 13 14 </td <td>10 10<</td> <td>100 100<td>100 100 300 h Mark <thm< td=""><td>100 100<td>100 100<td>100 100 200 h 100 h 100</td><td>100 100</td></td></td></thm<></td></td>	10 10<	100 100 <td>100 100 300 h Mark <thm< td=""><td>100 100<td>100 100<td>100 100 200 h 100 h 100</td><td>100 100</td></td></td></thm<></td>	100 100 300 h Mark Mark <thm< td=""><td>100 100<td>100 100<td>100 100 200 h 100 h 100</td><td>100 100</td></td></td></thm<>	100 100 <td>100 100<td>100 100 200 h 100 h 100</td><td>100 100</td></td>	100 100 <td>100 100 200 h 100 h 100</td> <td>100 100</td>	100 100 200 h 100	100 100

Figure 18-26 Search Vehicles in Parking Lot

- 1) Select a parking lot from the drop-down list.
- 2) Optional: Set vehicle information.

Label

Search marked or unmarked vehicles in the parking lot.

Country/Region

Select the country/region where the vehicle's license plate number is registered.

License Plate Number

Select **No License Plate** to search vehicles without license plate number; select **With License Plate** and enter a vehicle's license plate number or key word of license plate number.

Vehicle Owner

Enter the vehicle owner's name or keyword of name.

Vehicle Type

Select the type of the vehicle from the drop-down list.

Brand

Select the brand of the vehicle from the drop-down list.

Color

Select the color of the vehicle from the presented colors.

How to Open Barrier

It refers to how the barrier gate was opened when a vehicle exits the parking lot. **Manual** indicates that the a security guard manually controls the barrier gate to open after identifying the vehicle owner; **Automatic** indicates that the barrier gate was opened automatically after the capture unit recognizing the license plate number; **Barrier Not Open** indicates that the barrier gate was not opened after the capture unit recognizing the license plate number.

Vehicle List

Search vehicle passing records of vehicles in certain vehicle list(s).

Dwell Time

The parking duration of the searched vehicles in the parking lot.

Additional Information

The custom items of vehicle information you added.

3. Click Search.

The matched vehicles will be displayed in the right area.

IINote

You can click \equiv or \boxplus to switch between List Mode and Thumbnail Mode.

4. Perform the following operations if you need.

Delete Vehicles from Parking Lot	 Select a searched vehicle and click in to delete the vehicle from the parking lot. Click Delete All to delete all searched vehicles from the parking lot.
	Note
	After deleting a vehicle in the list, there will be one more vacant parking space in the parking lot.
Export Vehicle Information to PC	 Select a vehicle and click is to save the vehicle's information (CSV file), vehicle passing picture, and recorded file in your PC. The vehicle passing picture and recorded file will be saved in the same folder as the CSV file. Save information of all searched vehicles as a file in PC.

- a. In the top right corner, click **Export** to open the Export panel.
- b. Select **Excel** or **CSV** as the format of the exported file. Check **Export Picture** to save vehicles' pictures in your PC with the Excel file.
- c. Click **Browse** to select a saving path.
- d. Click Save.

INote

- Up to 500 records of parked vehicles with captured pictures can be exported at one time.
- Up to 100,000 records of parked vehicles without captured pictures can be exported at one time.

View Vehicle	Click a license plate number in the list to view the detailed information of
Information	the vehicle.

18.6.4 Search for Parking Records

On the platform, you can search for the parking records generated in a specific parking lot or the record of a specific vehicle by setting relevant search conditions according to actual needs, and perform further operations, such as viewing the detailed information of vehicles and exporting the records to your PC.

Steps

- 1. In the top left corner of the Client, select
 → All Functions → Investigation → Vehicle Search
 → Parking Record Search .
- 2. Set search conditions according to actual needs.

Parking Record Search	• •	1) Riger
Time		
Tota	. w.	
License Plate Number		
Vehicle		
18		
Roor 40		
Parking Space No.	No. 10	14.
Packing Status		
Search		

Figure 18-27 Parking Record Search Page

1) Set a time range.

i Note

You can select today, yesterday, current week, last 7 days, or last 30 days from the drop-down list to search for the records generated in a relevant period, or click **Custom Time Interval** to customize a time range.

- 2) **Optional:** Enter the license plate number of the vehicle.
- 3) Select a parking lot or **All** from the drop-down list.
- 4) Select a floor or All from the drop-down list.
- 5) **Optional:** Enter the parking space No.
- 6) Select the status of parking.
- 3. Click Search.

The matched record(s) will be displayed in the right area.

IINote

You can click \equiv or \blacksquare to switch between list mode and thumbnail mode.

4. Optional: In the upper-right corner, click Export to export the record(s) to your PC.

iNote

- Up to 500 parking records with captured pictures can be exported at one time.
- Up to 100,000 parking records without captured pictures can be exported at one time.

18.6.5 Search for Multiple Vehicles Under One Account Status

On the Control Client, you can search for the multiple vehicles under one account status of a specific parking lot or of a specific account by setting relevant search conditions according to actual needs. You can view the detailed information of the search results, including the information of the owner, the number of parking spaces allocated to an account, the validity of a vehicle's parking pass, the parking status of vehicles, etc.

Before You Start

Make sure that you have added multiple vehicles to the account to be searched for, and have related parking passes to the vehicles if needed. For more details. See the *User Manual of HikCentral Professional Web Client*.

Steps

In the top left corner of the Control Client, select
 → All Modules → Investigation → Vehicle Search → [m] Multiple Vehicles Under One Account Status Search → to enter the search page.





- 2. Set search conditions according to actual needs.
 - 1) Select a parking lot from the drop-down list.
 - 2) Optional: Enter the name of the vehicle owner.
 - 3) **Optional:** Enter the license plate number of the vehicle.
 - 4) Select the status of vehicle(s).

In

The vehicle(s) that are being parked in the parking lot.

Out

The vehicle(s) that have exited the parking lot.

5) Select whether the vehicle(s) are occupying the parking spaces allocated to the account.

Occupied

The vehicle(s) are occupying the parking spaces.

Not Occupied

The vehicle(s) are not occupying the parking spaces.

3. Click Search.

IIINote

The matched result(s) will be displayed in the right area.

4. Optional: In the upper-right corner, click Export to export the result(s) to you PC.

Chapter 19 Mobile Monitoring

The Mobile Monitoring function is for users to monitor driving vehicles, including locating vehicles to get their real-time GPS information and driving speed, talking to drivers via two-way audio, playing videos streamed from vehicle-mounted cameras, playing back the routes vehicles have traveled along, and searching for events and alarms triggered by vehicles. You can configure fence rules and deviation rules to assist you to monitor vehicles by regulating the areas where vehicles are allowed or not allowed to drive and the routes that vehicles are required to drive along.

19.1 Driving Monitoring

On the Driving Monitoring page, you can monitor driving vehicles to get their real-time information such as locations, speeds, and events. You can also play the live videos streamed from vehicle-mounted cameras, talk to drivers via two-way audio, track vehicles in real time, play back the routes vehicles have traveled along, and add vehicles to the Favorites list for quick and easy management.

In the top left corner of the Client, select $\blacksquare \rightarrow All Functions \rightarrow Surveillance \rightarrow Driving Monitoring to enter the Driving Monitoring page.$




Figure 19-1 Driving Monitoring Page

Vehicle List Pane

On the vehicle list pane, you can click **Expand Vehicle List** and then click $rac{1}{2}$ / $rac{1}{2}$ to view all/ online/located vehicles.

You can move the cursor onto a vehicle to view its real-time information, including its location, speed, etc, and can perform the following operations:

Operation	Step
Search for Vehicle	Enter key words in the search box and click 📷 to search for the specified vehicle.
Locate Vehicle	Click 🔝 to locate the vehicle on the map and click again to cancel locating it.
Play Back Route	Click 🔄 to play back the route the vehicle has traveled along.
Other	Click to open the operation menu and you can choose to play video, talk to a driver via two-way audio, track a vehicle in real time, play back traveled route, control alarm outputs, and add/remove a vehicle from the Favorites list. Note You can click rac to display the Favorites list.

Driving Monitoring Pane

You can click the icon of a located vehicle on the map to open the driving monitoring pane. On the pane, you can view the vehicle's real-time information including its location, speed, etc, and can perform the following operations:




Figure 19-2 Driving Monitoring Pane

Operation	Step
Cancel Locating Vehicle	Click 速 to cancel locating the vehicle.
Get Vehicle's Location	Click Get Location to get the vehicle's real-time location.
Play / Play Back Video	Click Play to play live videos or play back video recordings streamed from vehicle-mounted cameras.
Talk to Driver	Click Two-Way Audio to talk to the driver.
Track Vehicle	Click Track to track the vehicle in real time. You can click Stop in the upper-left corner of the vehicle-tracking page to stop tracking.
Play Back Route	Click Route and select a period and camera to play back the route recorded by the camera in the specified period.
Control Alarm Output	Click Alarm Output Control and then click <a>/ /to enable/disable the alarm output related to the vehicle.

Real-Time Event

The Real-Time Event table presents real-time events triggered by monitored online vehicles. Each record is attached with detailed information such as the license plate number, driver, event type, and GPS information. Besides, you can perform the following operations:

eta		0 100
Driver Number of Time Event Type GPS Info Driving Dire Alarm Trigg 0	Operation	
Smuletr O., 5	83 Q.	

Figure 19-3 Real-Time Event Table

Operation	Step
Locate Vehicle	Click 🙇 in the Operation column to locate a vehicle.
Center Vehicle	Click 🛃 in the Operation column to place a located vehicle in the center of the map.

Operation	Step
Search for Route	Click 🔍 in the Operation column to go to the Vehicle Route Search page to search for the route a vehicle has traveled along.
Select Event Type	Click to open the Settings pane and select the types of event to be reported to the platform.
Search for Driving Event	Click More to go the Driving Event Search page to search for driving events triggered in the past.

Location Info

The Location Info table presents the real-time locations of located vehicles. Each record is attached with detailed information such as the license plate number, GPS info, and driving direction. Besides, you can perform the following operations:

Real-Time Event	Location Info	o Get Location					
License Plate No.	Area	Time	GPS Info	Address	Driving Direction	Speed	Operation
		2021-10-22 07:20:31		Get Location	North	40km/h	28.62

Figure 19-4 Location Info Table

Operation	Step
Get Vehicle's Location	Click Get Location in the Address column to get the real-time location of a vehicle.
Auto Refresh Location	Check Auto Get Location to automatically refresh locations frequently.
Cancel Locating Vehicle	Click 🗈 to cancel locating a vehicle.
Center Vehicle	Click 🛃 to place a vehicle in the center of the map.

Map Management

You can perform the following operations on the map:

Operation	Step
Display Driving Rule	Click and select Fence Rule or/and Deviation Rule to display the fence area or/and route on the map.
Broadcast to Vehicle	Click 🛋 and select vehicle(s) to broadcast to them.
Measure Distance	Click 🥏 and specify the start point and end point on the map to measure the actual distance between them.
Full-Screen Display	Click 💥 to display the map in full-screen mode.
Zoom Map	Click $+$ / $-$ to zoom in/out on the map.

19.2 Mobile Monitoring Record

Mobile monitoring records include the routes vehicles have traveled along and the events triggered by them in a specified period. You can search for each of the two types of records, view the details of each record, and export records to your PC for further use.

19.2.1 Search for Vehicle Routes

You can search for the routes that vehicles have traveled along in the specified period, view detailed information of each record, play back routes, and export records to the PC.

Steps

- In the top left corner of the Client, select Search .
- 2. Select Select Driving Route Search on the left.
- 3. Set search conditions.
 - 1) Specify the period you want to search for vehicle routes in.
 - 2) Select vehicle(s).
 - 3) Optional: Switch on Speed Range and set a speed range.
 - 4) **Optional:** Switch on **Event Type** and click **b** to select event type(s).

i Note

All event types have been selected by default.

4. Click Search.

Wehicle Route Search						Edaport
Timi		Tere	Max.Speed (Artyl)	Min. Speed (brich)	Ryant Trippend	Operation
Let 10or - 100 - 210 - 0	1.1					5F (E)
Aufliche		2023 10-14 00:00:00- 2023 10-14 22 09:00	243	1.0	Ter.	SF 13
		2021-10-15-20-00000 2023-00-15-21-20-00		+	94	5 G
- · · · · · · · · · · · · · · · · · · ·		2021-10-16.0010048- 2021-89-16.2310481	1.1		644 C	S 0
 T d principal com 		2023-10-17 00:00:00- 0023-10-17 21:01:00			10.	37 EF
× 0 4 mm		2021-10-10-00-00-00-			100	SF (5)
 	L .	2021-10-19-0000109-2021-10-19-19-000		14	10	S G
	9	2023 10.21 202040- 2023 10.21 21 21 000			Tes	50
 C 4 30 		2021 10-21 00:00:00-		14	744.	s B
> c 4	1.4					S D
	ł					
Search	Int	11 100/Page				1 June Da

Figure 19-5 Vehicle Route Search

5. Optional: Perform the following operations.

Play Back Route	Click 🛒 to play back a route.
Export Record	Click 🖻 to export a single record to the PC. Click Export in the upper-right corner to export all records to the PC.
Other	Click \Rightarrow and more records generated in the specified period will be displayed. You can also click \subseteq to play back a route and click \boxdot to export a record to the PC.

19.2.2 Search for Driving Events

You can search for the event triggered by vehicles, view detailed information of each record, and export records to the PC.

Steps

- In the top left corner of the Client, select → All Functions → Investigation → Driving Record Search .
- 2. Select B Driving Event Search on the left.
- 3. Set search conditions.
 - 1) Specify the period you want to search for driving events in.
 - 2) Click 🗈 to select vehicle(s).

IINote

All vehicle(s) have been selected by default.

3) Click 🗈 to select event type(s).

IINote

All event types have been selected by default.

4) Click **Specify Area on Map** and draw an area on the map.

The platform will search for events triggered in the specified area.

4. Click Search.

Driving Esent Search										
Tini		then	e Pata.	Ans	Driver	Title	Beent Type	GPS Info	Driving Don.	Operation.
Table .	-					30.90.	Lave Decidior Warring		Varitmani	14 B
R	8				sector	1025-01-01-0	LAW Delation Mentry		Notice 1	<i>s</i> . e
8	-					305-10-21_	Lani Decedure Velamory		Notices	£ 5
						10110-01-	Anno In Anno Anno In		Note: 1	S.0
forest Type All overst types are ordered.	- 1				instant	20110-01-	Aprija fao Entry Detection		-	<i>x</i> 0
Maji Jora						100.001	Law Constant Manang		. Normani	8.8
Specify Avia on Higg					ternet	2025-10-21 -	Save Seriative Version		bertweet)	5.0
						1011-0121	Law Decision Henriq		Northeast.	S [0]
						8021-10-21	Agrica Rai		500 E	\$ 0
- Laure	_	Test state (10.740	121			111-1	1.1.9	16 D	the la

Figure 19-6 Driving Event Search

- **5. Optional:** Perform the following operations.
 - Play Back Route Click 🛒 to play back a route.

Export Record Click I to export a single record to the PC. Check record(s) and click **Export** in the upper-right corner to export them to the PC.

Chapter 20 Face and Body Recognition

The system supports facial recognition and comparison functions. After adding devices which support facial recognition, the devices can recognize faces and compare with the persons in the system.

Besides facial recognition, you can also add facial recognition servers to the system and set human body recognition tasks.

On the Control Client, the operator can view the real-time face comparison information during live view and see whether the detected persons match or mismatch the person information in the predefined face comparison group. The operator can also view the human body recognition information when viewing the live video of the cameras linked with the facial recognition server and configured with human body recognition.

20.1 View Detected and Matched Face in Live View

During live view of face recognition cameras, the detected faces will be displayed in the window. After setting the face comparison group and apply it to the camera, the face picture matched with the face in the face comparison group will display, showing the person details, captured picture, matched person's original picture, and similarity. If the detected person is not in the face comparison group, you can also add it to the face comparison group and apply the group to the device to take effect.

Before You Start

Add the required device and configure the face comparison group. Refer to the User Manual of HikCentral Professional Web Client.

Steps

INote

This function should be supported by the device.

2. Start live view.

- Drag a face recognition camera from the camera list on the left to the display window.
- Double-click a face recognition camera name to start the live view.

If a face is detected, it will be displayed on the right of the window. If he/she is not matched with any persons in the camera's linked face comparison groups, the capture time is marked with an orange background as follows.



Figure 20-1 Mismatched Person

3. View matched persons in different face comparison groups.

Example

For example, you can view the matched persons in blocklist and VIP list at the same time.

1) Click 🌆 tab to open the face comparison group list.

All the face comparison groups added to the system display.

2) Double click the face comparison group name in the list or drag it to the display window.

A blank panel of the face comparison group will display on the right of the display windows. If there are persons matched with the person in the face comparison group, the captured and original face pictures will display in this panel in pairs with similarity as follows.



Figure 20-2 Matched Persons

You can view the captured face picture, person's profile (configured in the Web Client) and the similarity. The person's name is shown on the profile.

4. Optional: View all the real-time face comparison events.1) Click at the bottom of the page to show the event list panel.

2) Click **Face Comparison** tab to view all the detected faces (including matched and mismatched persons).

INote

For mismatched persons, the picture's capture time is marked with an orange background as follows.



Figure 20-3 Mismatched Person

- 5. Optional: For the matched persons, view the person details.
 - In the matched face picture panel, click method to view the matched person details.
 - Click the face picture of matched person in the face comparison event list to view the person details.
 - In the all events list panel, select the person matched event and click in the Operation column to view the person information.
- **6. Optional:** If there are multiple cameras in live view, you can quickly find the camera which captures certain picture and view its live view.
 - In the matched face picture panel, click
 - In the Face Comparison event list, click the captured picture and click **Live View**.

The camera which captures this picture will be highlighted with a red frame.

7. Optional: For the captured pictures (mismatched or matched person), click the picture and click Search by Picture to search other pictures of this person. Refer to <u>Search Face Pictures by</u> <u>Picture</u> for more details.

20.2 Add Mismatched Person to Person Group

During live view, if a person is detected, but not matched with any persons in the face comparison group, and if you want the person to be recognized for the next time, you can add the person to the face comparison group. For example, if the detected person is a new arrived VIP, you can add the person to the VIP face comparison group and apply this group to the camera. For the next time, the camera will recognize the person's face and match her/him with the person information in the face comparison group.

Steps

1. In the top left corner of the Home page, select → All Modules → Surveillance → Monitoring and perform face comparison in live view.

IINote

For details, refer to *View Detected and Matched Face in Live View* .

- 2. Open the Add to Person Group panel.
 - At the bottom of the page, click **m** to unfold the All Events panel, and click **m** in the Operation column to open the Add to Person Group page.
 - Click the mismatched face pictures in Face Comparison event panel and click Add to Person Group.

Face Comparison Group	
AD1	
AD2	
face shaoxinyu	100
jingyuceshishengjiqian	
QWERTYUIO	
shaoxinyutest	
	Captured Face
ID	
6855845666	9
First Name	
Sender O Male O Female 💌 Un Email	iknow

Figure 20-4 Add to Person Group

- **3.** Select the face comparison group(s) you want to add this person to.
- **4.** Enter the person details, such as ID, first name, last name, gender, custom additional information, etc.
- 5. Click Add.

What to do next

Log into the Web Client and apply the face comparison group to the camera to take effect.

20.3 Face Search

Face pictures can be captured and stored on the platform. You can search captured face pictures by specific face feature; You can search face pictures by uploading a face picture; You can search matched face pictures with the face pictures in the comparison group; You can search face pictures by setting conditions such as frequently or rarely appeared persons.

Search Captured Pictures

You can search for face pictures by features such as age, gender, and wearing glasses or not. After search, you can view related pictures and video files (if available) and save video files to local storage.

Search by Picture

The captured face pictures can be stored in HikCentral Professional server or on the Recording Server. You can search for the target person in the captured pictures by uploading a face picture. You can also view the search results' related video files and save the related video files as evidence.

Search Matched Faces

You can search for the captured face pictures which are matched with the faces in specified face comparison groups. You can also export the related video footage to the local PC and save it as evidence to the SFTP server.

Search Persons by Frequency

You can search for the pictures of the frequently appeared persons of specific locations in a specific time period. The function is helpful for screening out the potential VIP customers in retail industry such as luxury stores. It can also be used to find out suspects who may commit crimes and thereafter notify the security personnel to be on guard in locations such as banks and jewelry stores.

20.3.1 Search Captured Face Pictures and Related Videos

The captured face pictures can be stored in SYS server or in the Recording Server. You can search for the target person in the captured pictures by person face features. You can also view the search results' related video files and save the related video files as evidence.

Steps

INote

Make sure your license supports facial recognition function, or turn to Home page of the Web Client, click **License Details** \rightarrow **Configuration** \rightarrow **Add** and then select the added cameras as facial recognition cameras. Otherwise, facial recognition function cannot perform normally in the system.

- In the top left corner of the Home page, select
 → All Modules → Investigation → Face Search .
- 2. Click Search Captured Pictures on the navigation panel on the left side of the page to enter the Search Captured Picture page.
- **3.** In the Time field, set the time period.
- You can select **Custom Time Interval** to specify the start time and end time for search.
- 4. Select the camera(s) to search the face pictures.
 - 1) Click 📑 to open the camera list panel.
 - 2) Select the current site or a Remote Site from the drop-down site list to show its cameras.
 - 3) Check the camera(s) you want to search.

IINote

Up to 200 resources can be selected for searching at the same time.

Time	
Today	~
Camera	D
l)	
Face Information	
Age Group	
Gender	
Wearing Glasses	
Smiling	
Temperature	
Temperature Status	
Wearing Mask or Not	

Figure 20-5 Search Captured Pictures

5. Optional: Set face features and the related parameters.

Age Group

After enabled, you can filter matched face pictures by age groups such as teenage, youth, middle-aged, and elderly.

Gender

After enabled, you can filter matched face pictures by gender (male or female).

Wearing Glasses

After enabled, you can filter matched face pictures by whether a person wears glasses/ sunglasses or not.

Smiling

After enabled, you can filter matched face pictures by whether a person is smiling or not.

Temperature

After enabled, you can set a threshold for searching out the matched persons whose skinsurface temperature equals to or exceeds the threshold.

Temperature Status

After enabled, you can filter matched persons by temperature status (normal or abnormal).

Wearing Mask or Not

After enabled, you can filter matched face pictures by whether a person wears a mask or not.

IINote

This function should be supported by the device. You can only enable face features that are supported by the device.

6. Click Search.

The search results will be displayed.

7. Optional: Perform the following operations for the searched pictures.

Select Time Period	Drag the slider to filter the results by setting a time period when a face picture is captured.
Change Display Order	 Select Chronologically to display the searched results in time order. Select Reverse Chronologically to display the searched results in reverse time order. Select Camera to display the searched results by cameras.
Switch Display Mode	 The searched results can be displayed in three modes, and you can switch among different display modes. Click Grid to view the searched results in thumbnails. Click List to view the searched results in the form of list. Click Map to display camera(s) on the map, and click a camera to view the searched results in thumbnails.
Generate Pattern	In the Map mode, select one or more pictures, and click Generate Pattern to display a certain person's pattern on the map. Note Make sure you have added resources on the map. For details about how to set the parameters, refer to the <i>HikCentral Professional Web Client User Manual</i> .
Open Auxiliary Screen	Click 📝 on the upper right corner to display the current page on an auxiliary screen.

8. Optional: Hover the cursor on a matched picture and perform the following operations.

Add to Person List	Click R and set the required parameters to add the person to the person list. For details about how to set the parameters, refer to the of <i>HikCentral Professional Web Client User Manual</i> .
Search Picture by Picture	Click Search by Picture to go to the Search by Picture page to search for the target person in the captured pictures by uploading a face picture. For detailed information, see <u>Search Face Pictures by Picture</u> .
Archive Search	Click Archive Search to go to the Archive Search page to search the person's archive.
Identity Verification	Click Identity Verification → To be Verified to verify the person's identity, or click Identity Verification → Target to set the person as a comparing target.

9. Optional: Click a captured picture to view detailed information such as gender, whether smiling, and age group, and you can perform the following operations.

Related Captures	Click Related Captures to display pictures captured during 30s before and after capturing the current picture.
View Picture and Video	Click 🖃 / 🖻 to view the large picture and the related video (if available).
	I INote
	For playback control instructions, refer to Normal Playback . Some icons

may not be available for face picture playback.

- 10. Optional: Export the matched pictures and videos to local storage.
 - 1) Select the matched results to be exported and click **Export**.
 - 2) Select the content to be exported.
 - 3) Select **Excel** or **CSV** as the format.
 - 4) (Optional) If the content to be exported contains video, select **MP4** or **AVI** as the video format.

IINote

MP4 format supports encryption. You can set a password to encrypt the video file for security purpose.

- 5) Set the saving path.
- 6) Click **Save** to add the downloading task to the download center.

IINote

For details about managing the downloading tasks, refer to Manage Downloading Tasks .

20.3.2 Search Face Pictures by Picture

You can search for face pictures by uploading a face picture. You can also view the video files related to the search results and save the related video files as evidence.

Steps

IINote

Make sure your license supports facial recognition function, or turn to Home page of the Web Client, click **License Details** \rightarrow **Configuration** \rightarrow **Add** and then select the added cameras as facial recognition cameras. Otherwise, facial recognition function cannot perform normally in the system.

- In the top left corner of the Home page, select Search .
 Search .
- 2. Click Search by Picture on the navigation panel on the left side of the page to enter the Search Captured Picture page.
- **3.** In the Time field, set the time period.

You can select **Custom Time Interval** to specify the start time and end time for search.

4. Select the camera(s).

- 1) Click 🗋 to open the camera list panel.
- 2) Select the current site or a Remote Site from the drop-down site list to show its cameras.
- 3) Check the camera(s) you want to search.

IINote

Up to 200 resources can be selected for searching at the same time.




Figure 20-6 Search by Picture

5. Optional: Set a picture for face picture searching, and you can upload one as desired.

- Enter a keyword of person name or person ID in the Person Name/ID field to search in the added persons.
- Click Upload Picture to upload a face picture from local PC.

INote

The uploaded picture should be in JPG format and picture size should be no larger than 1 GB.

The recognized face will be marked on the face picture.

- 6. Optional: Drag the slider to set the similarity.
- 7. Click Search.

The search results will be displayed.

8. Optional: Perform the following operations for the searched pictures.

Select Tir Period	ne Drag the slider to filter the results by setting a time period when a face picture is captured.
Change Display Order	 Select Chronologically to display the searched results in time order. Select Reverse Chronologically to display the searched results in reverse time order. Select Similarity to display the searched results in similarity order. Select Camera to display the searched results by cameras.
Switch Display Mode	 The searched results can be displayed in three modes, and you can switch among different display modes. Click Grid to view the searched results in thumbnails. Click List to view the searched results in the form of list. Click Map to display camera(s) on the map, and click a camera to view the searched results in thumbnails.
Generate Pattern	In the Map mode, select one or more pictures, and click Generate Pattern to display a certain person's pattern on the map.
	I Note Make sure you have added resources on the map. For details about how to set the parameters, refer to <i>HikCentral Professional Web Client User Manual</i> .
Open Auxiliary Screen 9. Optional: H	Click 🗹 on the upper right corner to open the current page on an auxiliary screen.
Add to Pe	click and set the required parameters to add the person to the person

Add to PersonClick and set the required parameters to add the person to the personListlist. For details about how to set the parameters, refer to HikCentral
Professional Web Client User Manual.

Search Picture by Picture	Click Search by Picture to go to the Search by Picture page to search for the target person in the captured pictures by uploading a face picture. For detailed information, see <u>Search Face Pictures by Picture</u> .
Archive Search	Click Archive Search to go to the Archive Search page to search the person's archive.
Identity Verification	Click Identity Verification → To be Verified to verify the person's identity, or click Identity Verification → Target to set the person as a comparing target.

10. Optional: Click a captured picture and the detailed information such as gender, whether to smile, and age group will be displayed, and you can perform the following operations.

Related Captures	Click Related Captures to display pictures captured during 30s before and after the captured picture.
View Picture and Video	Click 🔄 / 📼 to view the large picture and the related video (if available).
	Note
	For playback control instructions, refer to Normal Playback . Some
	icons may not be available for face picture playback.

- **11. Optional:** Export the matched pictures and videos to local storage.
 - 1) Select the matched results to be exported and click **Export**.
 - 2) Select the content to be exported.
 - 3) Select Excel or CSV as the format.
 - 4) (Optional) If the content to be exported contains video, select **MP4** or **AVI** as the video format.

Note

MP4 format supports encryption. You can set a password to encrypt the video file for security purpose.

- 5) Set the saving path.
- 6) Click **Save** to add the downloading task to the download center.

iNote

For details about managing the downloading tasks, refer to Manage Downloading Tasks .

20.3.3 Search Matched Faces

You can search for matched faces pictures with face pictures in specified face comparison group(s). You can also further filter the matched faces by skin-surface temperature and mask-wearing status for purposes such as infectious disease prevention. Exporting the related video footage to the local PC and saving it as evidence to the SFTP server are also supported.

Steps

- In the top left corner of the Home page, select
 → All Modules → Investigation → Face Search .
- 2. Click Search Matched Faces on the navigation panel on the left side of the page to enter the Search Matched Face page.
- 3. In the Time field, set the time period for searching.

IINote

You can select **Custom Time Interval** to specify the start time and end time for search.

4. Select the face comparison group(s) to search for the matched pictures.

IINote

Hover the cursor on a face comparison group and click $\underline{\mathbb{Y}}$ to select cameras linked with the group.

- 5. Optional: Enter a keyword of person name or person ID for result filtering.
- 6. Optional: Set the following conditions.

Skin-Surface Temperature

After enabled, you can set a threshold for searching out the matched persons whose skinsurface temperature equals to or exceeds the threshold.

Temperature Status

After enabled, you can filter matched persons by temperature status (normal or abnormal).

Wearing Mask or Not

After enabled, you can filter matched face pictures by whether a person wears a mask or not. **7.** Click **Search**.

The matched persons will be displayed and grouped by different face comparison groups, and you can view the person details.

8. Optional: Perform the following operations for the searched pictures.

Switch Display	The searched results can be displayed in three modes, and you can switch among different display modes.
Mode	 Click Grid to view the searched results in thumbnails. Click Map to display camera(s) on the map, and click a camera to view the searched results in thumbnails.
Generate Pattern	In the Map mode, select one or more pictures, and click Generate Pattern to display a certain person's pattern on the map.
	Note
	Make sure you have added the resource on the map. For details about how to set the parameters, refer to the <i>HikCentral Professional Web Client User Manual</i> .

9. Click 🔍 beside the original picture to perform secondary search.

Search Picture by Picture	Click Search by Picture to search for the target person in the captured pictures by uploading a face picture. For detailed information, see <u>Search</u> <u>Face Pictures by Picture</u> .
Search Archive	Click Archive Search to go to the Archive Search page to search the person's archive.
Verify Identity	Click Identity Verification → To be Verified to verify the person's identity, or click Identity Verification → Target to set the person as a comparing target.
Open Auxiliary Screen	Click Z on the upper right corner to open the current page on an auxiliary screen.

10. Optional: Click a captured picture and the detailed information such as gender, whether to smile, and age group will be displayed, and you can perform the following operations.

Related Captures	Click Related Captures to display pictures captured during 30s before and after the captured picture.
View Picture and Video	Click 🖃 / 🖻 to view the large picture and the related video (if available).
	For playback control instructions, refer to <u>Normal Playback</u> . Some icons may not be available for face picture playback.

- **11. Optional:** Export the matched pictures and videos to local storage.
 - 1) Select the matched results to be exported and click **Export**.
 - 2) Select the content to be exported.
 - 3) Select Excel or CSV as the format.
 - 4) (Optional) If the content to be exported contains video, select **MP4** or **AVI** as the video format.

INote

MP4 format supports encryption. You can set a password to encrypt the video file for security purpose.

- 5) Set the saving path.
- 6) Set and confirm the password for the ZIP file.
- 7) Click Save to add the downloading task to the download center.

IINote

For details about managing the downloading tasks, refer to Manage Downloading Tasks .

20.3.4 Search Persons by Frequency

You can search for the pictures of the frequently/rarely appeared persons captured by specific cameras in a specific time period. The function can be helpful for screening out the potential VIP customers in retail industry such as luxury stores. It can also be used to find out suspects who may commit crimes and thereafter notify the security personnel to be on guard in locations such as banks and jewelry stores.

Before You Start

Make sure you have configured frequently/rarely appeared person alarm on the device. For details, see the user manual of the device.

Steps

- In the top left corner of the Home page, select
 → All Modules → Investigation → Face Search .
- 2. Click Search Persons by Frequency on the navigation panel on the left side of the page to enter the Search Person by Frequency page.
- **3.** In the time field, select a time period or select **Custom Time Interval** to customize a time period for search.
- 4. Select Frequently Appeared Persons or Rarely Appeared Persons as the search type.
- **5.** Select the camera(s) to search the pictures of the frequently/rarely appeared persons.

Time	
Today	*
Туре	
Frequently A Rarely Appea	
Task	
Search	
All	
Appeared Times	

Figure 20-7 Search Persons by Frequency

1) **Optional:** Check **Include Sub-area** to allow the displaying of camera(s) in sub-areas.

2) Select areas and then select the camera(s) in these areas.

IINote

Up to 200 resources can be selected for search at the same time.

- 6. Enter a number in the Appeared Times field.
- 7. Click Search.

The frequently/rarely appeared persons will be listed on the right. You can view the photo, appeared time, and appeared times of each listed person.

- **8. Optional:** Click 🗈 to add the person to person list.
- **9. Optional:** Perform secondary search after clicking in the Operation column.

Search Picture by Picture	Click Search by Picture to search for the target person in the captured pictures by uploading a face picture. For detailed information, see <u>Search</u> <u>Face Pictures by Picture</u> .
Search Archive	Click Archive Search to go to the Archive Search page to search the person's archive.
Verify Identity	Click Identity Verification → To be Verified to verify the person's identity, or click Identity Verification → Target to set the person as a comparing target.
Open Auxiliary Screen	Click 🔀 on the upper right corner to open the current page on an auxiliary screen.

- **10.** Click a captured picture to view detailed information such as gender, whether to smile, and age group. You can also click **History Capture** to view the history captures of the selected camera.
- **11. Optional:** Filter related pictures and video footage by cameras.
 - 1) Click Filter Cameras to select camera(s).
 - 2) Click **OK**.

The pictures captured by the selected cameras and the video footage recorded by them will be displayed.

12. Optional: You can perform the following operations after filtering related pictures.

Related	Click Related Captures to display pictures captured 30s before and after
Captures	the captured picture.

View Picture Click / to view the large picture and the related video (if available).

IINote

For playback control instructions, refer to <u>Normal Playback</u>. Some icons may not be available for face picture playback.

- **13. Optional:** Export the matched pictures and videos to local storage.
 - 1) Select the matched results to be exported and click **Export**.
 - 2) Select the content to be exported.
 - 3) Select **Excel** or **CSV** as the format.

4) (Optional) If the content to be exported contains video, select **MP4** or **AVI** as the video format.

IINote

MP4 format supports encryption. You can set a password to encrypt the video file for security purpose.

- 5) Set the saving path.
- 6) Click **Save** to add the downloading task to the download center.

IINote

For details about managing the downloading tasks, refer to Manage Downloading Tasks .

20.4 Human Body Search

Human body pictures can be captured and stored on the platform. You can search captured face pictures by specific body feature, and you can also search human body pictures by uploading a picture.

Search Captured Pictures

You can search for persons by features such as age, gender, and wearing glasses or not. After search, you can view related pictures and video files (if available) and save video files to local storage.

Search by Picture

The captured human body pictures can be stored in HikCentral Professional server or on the Recording Server. You can search for the target person in the captured pictures by uploading a face picture. You can also view the search results' related video files and save the related video files as evidence.

20.4.1 Search Captured Human Body Pictures and Related Videos

You can search person pictures by setting person features such as age group and gender. For the searched results, you can view the related video files (if available) and save the video files to local storage. It can help to find out the target suspect in locations such as banks and jewelry stores when you know some features of a suspect.

Before You Start

Make sure you have added DeepinMind(s) or intelligent fusion server(s) in the web client.

Steps

- In the top left corner of the Home page, select Select All Modules → Investigation → Human
 Body Search .
- 2. Click 🔄 Search Captured Pictures on the left panel.
- **3.** In the Time field, set the time period.

JiNote

You can select **Custom Time Interval** to specify the start time and end time for search. The costumed time interval should be no more than 7 days.

4. Click 🗅 to select camera(s) from the pop-up camera list.

IINote

You can enter a key word in the search box to quickly find the target camera(s).

5. Optional: In the Person Information field, enable switch(es) of corresponding person features as desired such as age group, gender, and wearing glasses.

IINote

This function should be supported by the device. You can only enable person features that are supported by the device.

6. Click Search.

The searched results will be displayed chronologically.

7. Optional: For the searched results, you can perform more operation(s).

Switch Display Mode	 The searched results can be displayed in three modes, and you can switch among different display modes. Click Grid to view the searched results in thumbnails. Click List to view the searched results in the form of list. Click Map to display camera(s) on the map, and click a camera to view the searched results in thumbnails.
Change Display Order	 Select Chronologically to display the searched results in time order. Select Reverse Chronologically to display the searched results in reverse time order. Select Camera to display the searched results by cameras.
Search by Picture	 In the Grid mode, hover the cursor on the searched result, and click Search by Picture to start searching picture by picture.
	 Note For details, refer to <u>Search Human Body Pictures by Picture</u>. In list mode, click to perform a secondary search.
View Person Details	Put the cursor on the person picture, and you can view the capture details including person's age group, gender, whether wearing glasses, hair, tops type, etc.
	I II Note This function should be supported by the device.

View Picture and Video	Click the person picture to view the large picture and view the related video (if available).
	Note
	For details about playback control instructions, refer to Normal Playback .
Generate Pattern	Select one or more pictures, and click Generate Pattern to display a certain person's pattern on the map.
	Note
	Make sure you have added resources on the map. For details about how to set the parameters, refer to <i>HikCentral Professional Web Client User Manual</i> .
Export Results	You can export the searched results (both pictures and video footage) to local storage. Check one or more searched results, and click Export on the upper right corner to add the selected items to the download center.
	Note
	For details about managing the downloading tasks, refer to <u>Manage</u> <u>Downloading Tasks</u> .
Open Auxiliary Screen	Click 🔀 on the upper right corner to open the current page on an auxiliary screen.
8. Click a captured p	picture to view detailed information such as gender, whether to smile, and age an perform the following operations.

Download	Click Related Captures to download the pictures or videos.
View Picture	Click 🖬 / 🖻 to view the large picture and the related video (if available).
and Video	I Note
	For playback control instructions, refer to <u>Normal Playback</u> . Some icons may not be available for face picture playback.

20.4.2 Search Human Body Pictures by Picture

You can search human body pictures by uploading a face or human body picture. You can also view the video files related to the search results and save the related video files as evidence.

Before You Start

You have added DeepinMind(s) or intelligent fusion server(s) in the web client.

Steps

- In the top left corner of the Home page, select
 → All Modules → Investigation → Human Body Search .
- 2. Click Search by Picture on the left panel.
- **3.** In the Time field, set the time period.

IINote

You can select **Custom Time Interval** to specify the start time and end time for search. The costumed time interval should be no more than 7 days.

- **4.** Select the camera(s) to search the face picture.
 - 1) Click 📭 to open the camera list panel.
 - 2) Select a current site or Remote Site from the drop-down site list to show its cameras.
 - 3) Check the camera(s) you want to search.

IINote

Up to 200 resources can be selected for searching at the same time.




Figure 20-8 Search Human Body Pictures by Picture

5. Hover your mouse on the person information panel, and click **Upload Picture** to upload a face picture from local PC to set a picture for picture searching.

6. 7.

8.

Image: Search description of the searched results in the Griphic search description of the searched results will be displayed chronologically. Optional: For the searched results, you can perform more operation(s). Switch The searched results can be displayed in three modes, and you can switch among different display modes. Mode • Click Grid to view the searched results in thumbnails. • Click Grid to view the searched results in thumbnails. • Click Grid to view the searched results in thumbnails. • Click Grid to view the searched results in thumbnails. • Click Map to display camera(s) on the map, and click a camera to view the searched results in thumbnails. Search by • In the Grid mode, hover the mouse on the searched result, and click Search by Picture to start searching picture by picture. • In list mode, click □ to perform a secondary search. Image: Note For details, refer to Search Human Body Pictures by Picture . • In list mode, click □ to perform a secondary search. Image: Note For details, refer to Search Human Body Picture sup glasses, hair, tops type, etc. Image: Note This function should be supported by the device. View Picture and Video (fi available). Image: Note For details about playback control instructions, refer to Normal Playback . Change S		
The uploaded picture should be in JPG format and picture size should be no larger than 1 GB. Optional: Drag the slider to set the similarity. Click Search. The searched results will be displayed chronologically. Optional: For the searched results, you can perform more operation(s). Switch The searched results can be displayed in three modes, and you can switch among different display modes. Mode - Click Grid to view the searched results in thumbnails. - Click Kist to view the searched results in the form of list. - Click Map to display camera(s) on the map, and click a camera to view the searched results in thumbnails. Search by - In the Grid mode, hover the mouse on the searched result, and click Search by Picture to start searching picture by picture. - In list mode, click () to perform a secondary search. Image: Note For details, refer to Search Human Body Pictures by Picture . Put the cursor on the person picture, and you can view the capture details including person's age group, gender, whether wearing glasses, hair, tops type, etc. Image: Note This function should be supported by the device. View Picture and Video Click the person picture to view the large picture and view the related video (if available). Image: Note For details about playback control instructions, refer to Normal Playback . Select Chronologically to display the searched results in reverse	I Note	
Click Search. The searched results will be displayed chronologically. Optional: For the searched results, you can perform more operation(s). Switch Display Mode The searched results can be displayed in three modes, and you can switch among different display modes. Click Grid to view the searched results in thumbnails. Click List to view the searched results in the form of list. Click Map to display camera(s) on the map, and click a camera to view the searched results in thumbnails. Search by Picture In the Grid mode, hover the mouse on the searched result, and click Search by Picture to start searching picture by picture. In list mode, click Q to perform a secondary search. View Person Details View Picture Automotion should be supported by the device. View Picture Automotion should be supported by the device. Click the person picture to view the large picture and view the related video (if available). Click the person picture to view the large picture and view the related video (if available). Click the person picture to view the large picture and view the related video (if available). Change Display Order Select Chronologically to display the searched results in time order. Select Chronologically to display the searched results in the order. Select Camera to display the searched results by cameras. Select Camera to display the searched results by cameras.		ture should be in JPG format and picture size should be no larger than 1 GB.
Optional: For the searched results, you can perform more operation(s). Switch Display Mode The searched results can be displayed in three modes, and you can switch among different display modes. • Click Grid to view the searched results in thumbnails. • Click List to view the searched results in thumbnails. • Click Map to display camera(s) on the map, and click a camera to view the searched results in thumbnails. • Click Map to display camera(s) on the map, and click a camera to view the searched results in thumbnails. Search by Picture • In the Grid mode, hover the mouse on the searched result, and click Search by Picture to start searching picture by picture. • In list mode, click Q to perform a secondary search. Image: Porter of details, refer to Search Human Body Pictures by Picture . • In list mode, click Q to perform a secondary search. Image: Porter of details, refer to Search Human Body Pictures by Picture . • In the cursor on the person picture, and you can view the capture details including person's age group, gender, whether wearing glasses, hair, tops type, etc. Image: Porter of Anticle Porter and Video Click the person picture to view the large picture and view the related video (if available). Image: Porter and Video Click the person picture to view the large picture and view the related video (if available). Image: Porter and Video • Select Chronologically to display the searched results in time order. • Select Chronologically to		ne slider to set the similarity.
Display Modeamong different display modes.Mode- Click Grid to view the searched results in thumbnails. - Click List to view the searched results in the form of list. - Click Map to display camera(s) on the map, and click a camera to view the searched results in thumbnails.Search by Picture- In the Grid mode, hover the mouse on the searched result, and click Search by Picture to start searching picture by picture. - In list mode, click Q to perform a secondary search.View Person DetailsPut the cursor on the person picture, and you can view the capture details including person's age group, gender, whether wearing glasses, hair, tops type, etc.View Picture and VideoClick the person picture to view the large picture and view the related video (if available).View Picture and VideoSelect Chronologically to display the searched results in time order. - Select Camera to display the searched results by cameras.Change Display Order- Select Camera to display the searched results in time order. - Select Camera to display the searched results by cameras.GenerateSelect one or more pictures, and click Generate Pattern to display a certain		
Pictureby Picture to start searching picture by picture. • In list mode, click on to perform a secondary search.Image: Picture and Picture	Display	 among different display modes. Click Grid to view the searched results in thumbnails. Click List to view the searched results in the form of list. Click Map to display camera(s) on the map, and click a camera to view the
View Person DetailsPut the cursor on the person picture, and you can view the capture details including person's age group, gender, whether wearing glasses, hair, tops type, etc.View Picture and VideoClick the person picture to view the large picture and view the related video (if available).View Picture and VideoClick the person picture to view the large picture and view the related video (if available).Change Display OrderSelect Chronologically to display the searched results in time order. Select Camera to display the searched results by cameras.GenerateSelect one or more pictures, and click Generate Pattern to display a certain	•	 by Picture to start searching picture by picture. In list mode, click to perform a secondary search.
Detailsincluding person's age group, gender, whether wearing glasses, hair, tops type, etc.View Picture and VideoThis function should be supported by the device.View Picture and VideoClick the person picture to view the large picture and view the related video (if available).DetailsSelect the person picture to view the large picture and view the related video (if available).Change Display OrderSelect Chronologically to display the searched results in time order. Select Camera to display the searched results by cameras.GenerateSelect one or more pictures, and click Generate Pattern to display a certain		For details, refer to <u>Search Human Body Pictures by Picture</u> .
View Picture and VideoThis function should be supported by the device.View Picture and VideoClick the person picture to view the large picture and view the related video (if available).Image: Display OrderNote For details about playback control instructions, refer to Normal Playback .Change Display Order• Select Chronologically to display the searched results in time order. • Select Reverse Chronologically to display the searched results in reverse time order. • Select Camera to display the searched results by cameras.GenerateSelect one or more pictures, and click Generate Pattern to display a certain		including person's age group, gender, whether wearing glasses, hair, tops
View Picture and VideoThis function should be supported by the device.View Picture and VideoClick the person picture to view the large picture and view the related video (if available).Image: Display OrderNote For details about playback control instructions, refer to Normal Playback .Change Display Order• Select Chronologically to display the searched results in time order. • Select Reverse Chronologically to display the searched results in reverse time order. • Select Camera to display the searched results by cameras.GenerateSelect one or more pictures, and click Generate Pattern to display a certain		i Note
 and Video (if available). in Note For details about playback control instructions, refer to <u>Normal Playback</u>. Change Select Chronologically to display the searched results in time order. Select Reverse Chronologically to display the searched results in reverse time order. Select Camera to display the searched results by cameras. Generate 		
For details about playback control instructions, refer to Normal Playback .Change Display Order• Select Chronologically to display the searched results in time order. • Select Reverse Chronologically to display the searched results in reverse time order. • Select Camera to display the searched results by cameras.GenerateSelect one or more pictures, and click Generate Pattern to display a certain		
For details about playback control instructions, refer to Normal Playback .Change Display Order• Select Chronologically to display the searched results in time order. • Select Reverse Chronologically to display the searched results in reverse time order. • Select Camera to display the searched results by cameras.GenerateSelect one or more pictures, and click Generate Pattern to display a certain		Note
 Display Order Select Reverse Chronologically to display the searched results in reverse time order. Select Camera to display the searched results by cameras. Generate Select one or more pictures, and click Generate Pattern to display a certain 		
	Display	 Select Reverse Chronologically to display the searched results in reverse time order.

	I INote
	Make sure you have added resources on the map. For details about how to set the parameters, refer to <i>HikCentral Professional Web Client User Manual</i> .
Export Results	You can export the searched results (both pictures and video footage) to local storage. Check one or more searched results, and click Export on the upper right corner to add the selected items to the download center.
	i Note
	For details about managing the downloading tasks, refer to <u>Manage</u> <u>Downloading Tasks</u> .
Open Auxiliary Screen	Click 🗹 on the upper right corner to open the current page on an auxiliary screen.
9. Click a captured p	picture to view detailed information such as gender, whether to smile, and age an perform the following operations.
Related Captures	Click Related Captures to download the pictures or videos.
View Picture	Click 🔤 / 🖻 to view the large picture and the related video (if available).
and Video	Note
	For playback control instructions, refer to <u>Normal Playback</u> . Some icons may not be available for face picture playback.

20.5 Archive Search

The system will save the features and information (including captured picture and video) of the captured person as archive. You can search the related archives of a face picture to check the captured pictures or videos of similar persons in the library. You can also check whether a person is a stranger.

Before You Start

Make sure you have added a DeepinMind server to the system and have configured capturing camera and face comparison group for it.

Steps

IINote

By default, the archive will be kept for 3 months.

- In the top left corner of the Home page, select
 → All Modules → Investigation → Identity Search .
- 2. Click **Archive Search** in the navigation panel on the left side to enter the Archive Search page.
- **3.** Select a face comparison group in the Face Picture Library field, you can also check stranger group.
- 4. Upload a face picture in the Person Information field.
- 5. Drag the slider of the similarity to set a similarity.
- 6. Click Search.

Pictures of which the similarity is larger than the configured one will be displayed on the right panel. Hover the cursor on a searched picture and the details (e.g. group name, gender, etc) of the picture will appear, and strangers' picture details are different from that of the face comparison group.




Figure 20-9 Archive Search

7. Optional: Hover the cursor on a matched picture and click it to perform secondary search.

Search Captured Picture	Click Search Captured Picture to go to the Face Search page to search the captured pictures related with the searched face picture by setting searching conditions.
Search Archive	Click Search Archive to go to the Archive Search page to search the searched person's archive.
Verify Identity	Click Identity Verification \rightarrow To be Verified to verify the person's identity, or click Identity Verification \rightarrow Target to set the person as a comparing target.

8. Optional: Perform the following operation(s).

View Picture and Video	Click a matched picture to view more captured pictures and related videos.
Export Archive Search Report	Check searched pictures and then click Export to save the data in the current computer. Select Excel if you want to save the searched picture or video.
Filter Capture Time	Click a matched picture and click Filter Capture Time to set the time period when the picture and video are captured.

20.6 Identity Verification

The control client provides picture-to-picture comparison and picture-to-group comparison, which means you can know the similarity between two faces on two different pictures, or whether a person is a member of an existing face comparison group,.

20.6.1 Compare with Face Comparison Group

When you are not sure about a person's identity, you can compare the his/her face picture with those of the face comparison group to identify him/her.

Before You Start

Make sure you have added a DeepinMind server to the system and have configured capturing camera and face comparison group for it.

Steps

- In the top left corner of the Home page, select → All Modules → Investigation → Identity Search .
- 2. Click **Identity Verification** to enter the Identity Verification page.
- 3. Upload the face picture you want to identify.
- 4. Select Face Comparison Group in the Compare with field.
- 5. Select a face comparison group in the list.
- 6. Optional: Set epidemic-related parameters.

Temperature

After enabled, you can set a threshold for searching out the matched persons whose skinsurface temperature equals to or exceeds the threshold.

Temperature Status

After enabled, you can filter matched persons by temperature status (normal or abnormal).

Wearing Mask or Not

After enabled, you can filter matched person who wear mask and those who don't. **7.** Drag the slider of the similarity to set a similarity.




Figure 20-10 Compare with Face Recognition Group

8. Click Search.

Pictures of which the similarity is larger than the configured one will be displayed on the right panel.

- 9. Optional: Click Add Person to add the person to person list.
- **10. Optional:** Hover the cursor on a matched picture and click it to perform secondary search.

Search Captured Picture	Click Search Captured Picture to go to the Face Search page to search the captured pictures related with the searched face picture by setting searching conditions.
Search Archive	Click Search Archive to go to the Archive Search page to search the searched person's archive.
Verify Identity	Click Identity Verification \rightarrow To be Verified to verify the person's identity, or click Identity Verification \rightarrow Target to set the person as a comparing target.

20.6.2 Compare with Specific Picture

You can also compare two face pictures to see whether they are the same person according to the similarity.

Before You Start

Make sure you have added a DeepinMind server to the system and have configured capturing camera and face comparison group for it.

Steps

- In the top left corner of the Home page, select → All Modules → Investigation → Identity Search .
- 2. Click **Identity Verification** to enter the Identity Verification page.
- **3.** Upload the face picture you want to identify in the **Person Information** field on the top of the panel.
- 4. Select Picture in the Compare with field.
- 5. Upload a picture in the **Person Information** field on the bottom of the panel.




Figure 20-11 Compare with Specified Picture

INote

You can upload a picture with more than one face, and the client will tell the similarity between the first picture and all faces in this picture.

- 6. Drag the slider of the similarity to set a similarity.
- 7. Click Search.

The face picture(s) on the second uploaded picture will be displayed on the right panel, and the similarity between persons on the first-uploaded picture and second-uploaded is displayed.

- 8. Optional: Click Add Person to add the person to person list.
- **9. Optional:** Hover the cursor on a matched picture and click it to perform secondary search.

Search Picture by Picture	Click Search Picture by Picture to go to the Face Search page to search for a target person in the captured pictures by uploading a face picture. For detailed information, see <u>Search Face Pictures by Picture</u> .
Search Archive	Click Search Archive to go to the Archive Search page to search the searched person's archive.
Verify Identity	Click Identity Verification → To be Verified to verify the person's identity, or click Identity Verification → Target to set the person as a comparing target.

Chapter 21 Security Control

A security control device detects people, vehicles, etc., entering a pre-defined region, triggers events and alarms, and reports events/alarms information (such as location) to security personnel.

On the Control Client, the operator can view the video of the radar's related cameras, arm & disarm partitions, bypass zones, etc. If a panic alarm is triggered, the operator can handle the request on the Control Client.

21.1 Start Live View of Radar's Calibrated Camera

You can start live view of a radar's calibrated camera to view the image of the radar's detection area.

Before You Start

Make sure you have configured at least one calibrated camera for the radar. See User Manual of HikCentral Professional Web Client for details about configuring calibrated camera.

Steps

- In the top left corner of the Home page, select
 → All Functions → Surveillance → Monitoring .
- 2. Select Live View.
- **3.** Double-click a radar's name or drag a radar from the area list to the display area to start the live view of its calibrated cameras.

The image of one calibrated camera will be displayed in the display window.




Figure 21-1 Live View of Radar's Calibrated Cameras

4. Optional: Perform the following operation(s).

Arming Control	The arming status of the radar will be displayed in the upper-right corner of the live view window. Click 🎆 to arm the radar; click 🚮 to disarm a radar.
Switch Calibrated Camera	Hover the cursor on the thumbnail to display other calibrated cameras' thumbnails, and then click one of the thumbnail to display it in the display window.
Locate on Map	Click 📓 in the lower-left corner of the live view window to show the map where the radar is added, so that you will see the moving pattern of the one who intruded the detection area.

iNote

- A prompt about the current arming status will appear if there is no calibrated camera linked to the radar when you arm the radar.
- A prompt about the failure of arming will appear if someone is in the radar's detection area when you arm the radar.

21.2 Perform Arming Control for Resources

You can arm or disarm the partitions (areas) of the security control devices and radars via the Control Client. After arming the partitions (areas), the current Control Client can receive the triggered alarms in the partitions (areas). You can also bypass or recover bypass for the alarm

inputs (zones) in the partitions (areas) if necessary. For armed radars, if an object enters its detection area, an event/alarm will be triggered to inform you.

In the top left corner of the Home page, select $\blacksquare \rightarrow All Functions \rightarrow Tool \rightarrow Arming Control$.

Partition (Area)

In the Resource area, click the number of partitions (areas) to view the details and then arm/ disarm the partition (areas) or clear the generated alarms in the partitions (areas) as needed.

IINote

The operations only control the alarm detection on the current Control Client.

Winning Control											a.
#Aarm 272 		0	0		R Testa		169	15 April 10 April 10	1	2	
Stards.	q	All (15)	Duered(11)	g Am V	⊛ Diar	4	Alarm				Q
 O HitControl Professional 			Resource Na.	Device Arm	ing Status 1	τ	Status 1				
Variable a			Aves 3	State of the	mid		•				
C. Designation		5 2	Area 1	manager of the	med		•				
Participation of the second se		5 -	Area 2	manufacture One	and a						
a seemanne											
5. 000		2.0	Area 3	And And	1000						
1. Marr		3	Avea 1	Harrison Dea	thed		•				
R. Marrie		(H. 11)	Area 2	CONTRACTOR ON	med		•				
S. CONTRACTOR		5	Area 3	SHOWING THE Day	read		•				
A construction		10	Area 1	minimum in the	inal		•				
S. CONTRACTO							1.1				
A seminarity of the		100	(W)								

Figure 21-2 Arm & Disarm Partition (Area)

Instant Arming

It is used when people leave the detection area. The zone will be immediately triggered when it detects event or alarm with no delay and notify the security personnel.

Stay Arming

It is used when people stay inside the detection area. During stay arming, all the perimeter burglary detectors (such as perimeter detector, magnetic contacts, curtain detector in the balcony) will be turned on. Meanwhile, the detectors inside the detection area are bypassed (such as PIR detectors). People can move inside the area and not trigger an event or alarm.

Away Arming

It is used when people leave the detection area. Event or alarms will be activated when the zone is triggered or tampered. For delayed zone, the alarm will not be activated when the zone detects triggering event during entry/exit delay.

Alarm Clearing

Select one or multiple partitions (areas) and click **Alarm Clearing** to clear the generated alarms in partitions (areas).

Alarm Input

In the Resource area, click the number of alarm inputs to view the details and then perform the operations such as bypass or bypass recovery for the zone that the alarm input belongs to.

Bypass Zone

When some exception occurs for the zone, and other zones can work normally, you need to bypass the abnormal zone to turn off the protection of it. Otherwise, you cannot arm the security control partition (area) which the zone belongs to.

Hover over the alarm input and click $\ensuremath{\square}$ to bypass the zone.

Bypass Recovery

When you want to recover the zone that is bypassed to make it work normally, select alarm input as triggered source and find the alarm input (zone) of the security control partition (area). Hover over the zone and click so to recover zone to normal status.

Radar

In the Resource area, click the number of radars to view the details and then arm or disarm one or multiple radars as needed.

21.3 Handle Panic Alarm from Panic Alarm Station

A panic alarm station is mainly installed in the areas with the crowd or high incidence of cases, such as schools, tourist attractions, hospitals, markets, and parking lots. When the emergency happens or someone asks for help, the person can press panic button to send alarm to the monitoring center, and the operator in the center will take the appropriate actions.

IINote

You should first set an alarm triggered by alarm input for the panic alarm station via the Web Client. For details, refer to User Manual of HikCentral Professional Web Client.

If someone presses the panic button on the panic alarm station, a window will pop up on the Control Client as follows:

	1.16		Video Operatio	
riggered By				
Planne Pla				
Event Camera (Offline			
Device;	16-			
gering Time	2021/10/15 15:42:43	3		
goring Time_	2021/10/15 15:42:43	1		
fleenack:				
			NO VIDEO	NO VIDEO
1999 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 -	Additional Informat	tion S		
	Unacknowledged			-
Alarn Hisrityi	High	<u></u>		
Alarm Type:	Nonet	. w		
famels	1	- 11		
		8	Go to Alarm Time Dive View	Display Alarm Stop

Figure 21-3 Panic Alarm

Function	Description
Acknowledge Alarm	Click Acknowledge to acknowledge this panic alarm.
Forward Alarm	Click Forward to forward this alarm to anther person.
Send Alarm Email	Click Send Alarm Email to send an alarm email to a specific recipient.
Alarm Output Control	Click Alarm Output Control and turn on/off the switches to control the status of alarm outputs.
Stop Broadcast	Click Stop Broadcast to stop broadcast of specific terminals.

Chapter 22 Check Alarm and Event

The alarm information (for example, motion detection alarm information) received by the Control Client displays. You can check the detailed information of the event or alarm, view the alarm linked video, manage the related information, and so on.

INote

You should configure the event or alarm settings via the Web Client before you can check the related information and linkage actions via the Control Client. For detailed configuration of event and alarm settings, refer to *User Manual of HikCentral Professional Web Client*.

22.1 View Resources' Real-Time Alarms

The Alarm Center module will display the real-time alarm information from the managed resources, such as motion detection, video loss, and video tampering alarm. You can check the alarm details and view alarm-related video and picture if configured.

iNote

Before receiving alarms from devices on the Control Client, you should arm devices. For details, refer to *Perform Arming Control for Alarms*

In the top left corner of the client, select $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Alarm Center .

M	Y I		🖸 Auto De 🖂 Se	able Pyp-up Window	W Area	in Church	UK Tran	foet @ set
Latent Alaem(48) Igno	et Alexandi Brain	e Alarms Dapla. Sie Bench	Achtronitelge				0.	entries. Henry April
Mak : T	Alam Name 1	Alarm Printly 1 T	Alam Time (Clarit) 🕫	Alarm Times	Sector 1		Area 1	Tripper Event :
		in the second	2021/10/26 11/27/04	34				Temperature Alarm
		High	2021/10/06 11:26:45	1				Mattern Detection
	• A	Hat	2021/10/06 11:06:16	5				Motion Detection
a		High	2021010;06 11:22:07	1				Autio Emiption Detect
G P		15 March	2001/10/06 11/18:59	1				Auto Emplain Detail
Aster Value & Picture		ALC: NOT THE OWNER.	C May			-	-	
	-		ín	_	I	e d	8 7	SAN

Figure 22-1 Alarm Center

You can select a site from the drop-down list in the top left corner to display alarms of the selected site, and you can click **Latest Alarm** or **Ignored Alarm** to view the latest received alarms or alarms that cannot be received by the current Control Client.

IINote

Selecting site is only available for the Central System with the Remote Site Management module.

Operation	Description
Mark Alarm	Click <a>F to mark alarms if some alarms are important or need further operations.
View Alarm Details	View alarm details in the table of Alarm Center page or click an alarm name to view the details of a specified alarm (refer to View Pop-up Window Triggered by Alarm for details).
	Alarm Priority
	The priority for the alarm according to the priority settings when adding the alarm on the Web Client.
	Alarm Time (Client)
	The time of Control Client when the alarm starts.

Table 22-1 Operations in Alarm Center

Operation	Description
	Alarm Times
	Shows how many times the alarm has been triggered.
	Source
	The resource that occurred the alarm.
	Triggering Event
	Display the type of the event that triggered the alarm.
	Alarm Status
	The current status of the alarm, including stopped, started, and abnormal.
Operations of an Alarm	Go to Alarm Search Page : Click 🚉 in the Operation column to go to the Event & Alarm Search page to search the current alarm by setting conditions.
The available operation changes according to the alarm linkage of the source. For detailed configuration, refer to User Manual of HikCentral Professional Web Client.	Linkage Action : Click in the Operation column to start live view or playback of the related cameras of the alarm and view the captured pictures. During the live view, you can click to enter the camera's visual tracking mode. See <i>User Manual of</i> <i>HikCentral Professional Web Client</i> for details about configuring visual tracking.
	Two-Way Audio : Start two-way audio with the alarm source of the current site or Remote Sites.
	Display on Smart Wall : Display the alarm video on the smart wall.
	Ignore : Click in the Operation column to ignore the selected alarm, so the current Control Client will not receive this alarm during the ignorance duration even though it is triggered.
	Accept: Click 📠 in the Operation column to accept the alarm, so the current Control Client can receive this alarm when it is triggered.
	Disable : Click ⊖ in the Operation column to disable the selected alarm, so the platform cannot receive and record this alarm during the disabling duration even though it is triggered.
	Enable : Click in the Operation column to enable the alarm, so the platform can receive this alarm and you can view the alarm information on any clients.

Operation	Description
	Export : Click is in the Operation column to download the alarm details, including alarm information, alarm picture, linked video, linked map, etc.
	Forward : Click 🖆 in the Operation column to forward the alarm to other users for acknowledgment.
Filter Alarms	Set filter conditions to display the required alarms only.
	Marking Status
	Mark the alarm information and the marked items can be filtered.
	Alarm Priority
	The priority including low, medium, high, and custom level which indicates the urgent level of the alarm.
	Alarm Status
	The status of the alarm includes Start , Stop and Abnormally Stopped . Start indicates the alarm has not stopped yet; Stop indicates the alarm has stopped; and Abnormally Stopped indicates the alarm has stopped abnormally.
	Alarm Displayed on Smart Wall
	Check Show Alarms Displayed on Smart Wall Only to filter the alarms which are set to be displayed on the smart wall.
Sort Alarms	Click the column name of the alarm list and select a property to sort the alarms by the selected property.
View Alarm Related Video and Map	Select an alarm, and the alarm-related video or picture (if any) shows on the display window and the alarm source related map (if any) appears as well. You can select Display Related Video & Map/Display Related Video Only/Display Related Map Only in the top right corner of the Alarm Center to show different display windows.
	For the related video & picture window, you can click Set in the top right corner of the window to show the video or picture preferred.
Acknowledge an Alarm	Click the name of an alarm to open the alarm details window, set parameters (e.g., alarm priority, alarm category, and remark), and click Acknowledge to acknowledge the alarm.

Operation	Description
	Note Refer to <u>View Pop-up Window Triggered by Alarm</u> for details.
Batch Acknowledge Alarms	 Check alarms in the alarm list, and then click Batch Acknowledge to open the Batch Acknowledge window. (Optional) Set the alarm priory and alarm category. (Optional) Enter a remark about the alarm acknowledgment. Click OK. Note
	Up to 100 alarms can be acknowledged at a time.
Turn On/Off Alarm Sound	When the Control Client receives an alarm, the PC running the Control Client will play the alarm sound. You can turn on/off the alarm sound by checking or unchecking Audio On in the top of the Alarm Center page.
	Note This configuration will not be changed after restarting the Control Client.
Enable/Disable Pop-up Alarm Window	For the alarm configured with the pop-up window, a window will pop up, showing the alarm details, when the Control Client receives the alarm. You can disable or enable the pop-up window by checking or unchecking Enable Pop-up Window in the top of Alarm Center page.
	Note This configuration will not be changed after restarting the Control Client.
Arming Control	Click Arming Control in the top right corner of the Alarm Center to accept/ignore or enable/disable the configured alarm rules of selected resource(s), arm or disarm the partitions (areas) of the security control devices and radars, and bypass or recover bypass for the alarm inputs (zones) in the partitions (areas).
	Note For details, refer to <u>Perform Arming Control for Alarms</u> and <u>Perform Arming Control for Resources</u> .

Operation	Description
Manually Trigger User-Defined Event	Click Trigger Event in the top right corner of the Alarm Center page to manually trigger a user-defined event and activate a series of actions. See <u>Manually Trigger User-Defined Event</u> for details.
Enter Alarm Overview Page	Click Overview in the top right corner of the Alarm Center page to enter the Alarm Overview page to view the alarm analysis report, top 5 alarms, and top 5 warning zones. See <u>Alarm</u> <u>Overview</u> for details.
View History Alarm	Click History Alarm to enter the Alarm & Event Search module to search the history alarms. See <u>Search Event and Alarm Logs</u> for details.
Customize Displayed Columns of Alarm List	 Click M to open the Customize Column Name panel. Check the column name(s) to display. Intermark Intermark Intermark The Alarm Name is displayed by default, and you cannot uncheck it. Click OK to save the settings.
Go to the Configuration Page of Alarm Center	Click Set on the top-right corner of the Alarm Center to change the settings of the linkage action, alarm sound, and alarm list. See <u>Set Linkage Action Parameters</u> , <u>Set Alarm Sound</u> , and <u>Customize Icons on Alarm Center</u> .

22.2 View Pop-up Window Triggered by Alarm

After configuring the required settings on the Web Client and Control Client, the alarm window will open when the corresponding event/alarm is triggered. You can view the alarm time, the source device which triggered the alarm, the triggered event, and alarm status, etc.

Before You Start

Make sure you have enabled the alarm linkage of **Trigger Pop-up Window** on the Web Client, and enabled the pop-up window function in the Alarm Center on the Control Client. For setting this alarm linkage, refer to the *User Manual of HikCentral Professional Web Client*.

Steps

1. View the alarm details including alarm source, alarm time, triggered event type, alarm status, etc., in the pop-up window when an alarm is triggered.




Figure 22-2 Alarm Triggered Pop-Up Window

- **2. Optional:** If you have set the additional information for the area where the alarm is triggered, click **Expand Area Additional Information** to display it.
- **3. Optional:** Set the alarm priority and the alarm category according to the detailed alarm information.
- 4. Optional: Enter a remark for the alarm according to actual needs.

Example

You can enter "False alarm triggered by leaves" when you have checked the alarm details and found that it is a false alarm.

5. Click **Picture/Video/Map/Operation Logs** to view the alarm-related cameras' captured pictures, the playback or live view when the alarm occurred, view the camera/alarm input location on the map (if configured), and view operation logs (i.e., forwarding, acknowledgment) of the alarm.

INote

When viewing the recorded video files of the related camera, you can click **Go to Alarm Time** to play the video from the alarm time. You can also click **Live View** to view the live video of the related cameras, or click **Display on Smart Wall** to play the playback on smart wall.

6. Click Acknowledge to acknowledge the alarm.

The alarm status becomes Acknowledged.

7. Optional: Click Forward to forward the alarm to other users of the platform.

Example

For some specific alarms, you can forward them to other users for acknowledgment. And you can set the priority to High to remind other users of acknowledging the alarms in the highest priority.

- **8. Optional:** Click **Send Alarm Email**, select an email template, and enter the recipient(s) of the alarm and remarks to send an email containing the information about this alarm to the selected recipients.
- **9. Optional:** Click **Alarm Output Control** to enable or disabled the linked alarm outputs if you have set linked alarm outputs in the alarm rule.

Example

If a sounder is linked in the alarm rule, when the alarm is triggered, you can turn on or off the sounder.

10. Optional: Click **Broadcast Control** to broadcast the alarm information from the Remote Site to the connected devices.

IINote

This function is only supported by the Central System with the Remote Site Management module.

- **11. Optional:** Click < > to view the previous or next alarm information.
- **12. Optional:** Uncheck **Enable Pop-up Window** to disable pop-up window when a new alarm is triggered.

iNote

When the pop-up window remains open, the later alarm, if the alarm priority is higher, will be displayed in the pop-up window, and replace the earlier one.

13. Optional: Check **Full Screen** to display the pop-up window in full-screen mode by default.

22.3 Manually Trigger User-Defined Event

The platform provides user-defined event which is used if the event you need is not in the provided event and alarm list, or the generic event cannot properly define the event received from third-party system. On the Control Client, you can trigger a user-defined event manually and it will activate a series of actions according to the settings on Web Client.

Before You Start

Add the user-defined event to the platform and determine what happens when you manually trigger it, such as setting it as the alarm source, as start/end of the alarm's arming schedule, or as the alarm linkage actions. For details, refer to *User Manual of HikCentral Professional Web Client*.

Steps

1. On the Alarm Center page, click **Trigger Event** in the top right corner to open the Select User-Defined Event window.

iNote

You can also click 🔜 in the top right corner of live view or playback page to open the Select User-Defined Event window.

The user-defined events added to the platform will be displayed.

2. Select the event you want to trigger and click OK.

22.4 Perform Arming Control for Alarms

You can accept/enable and ignore/disable the configured alarm rules of selected resource(s). After accepting/enabling one alarm rule, the current Control Client / platform can receive the triggered alarm information from the alarm source. If you ignore/disable one alarm rule, the current Control Client / platform cannot receive this alarm from the alarm source.

Steps

i Note

You can also perform arming control for security control devices (such as arming/disarming partitions, bypassing zones, etc.) and radars. For details, refer to <u>Security Control</u>.

- **1.** In the top left corner of the client, select $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Alarm Center .
- 2. On the top right of the Alarm Center, click Arming Control to open the Arming Control window.

INote

You can also select $\blacksquare \rightarrow$ Tool \rightarrow Arming Control to open the Arming Control window.

3. On the Arming Control window, click a number on the Alarm tab.

1		-			
356	5 0	0	169	15	2
	0				
	Trapped by Cards		and the second sec		544
0.1111	21 (#)				
Press interest					100
	And the second states and the second states				
	C Bank, T Aper Pauly, T Ban		ad X Deciptor		
(a.)	di terre dat	Barris, Same			
14-	inter in				
141	Nami In	suprise, ferming loader			
14-1	Name of	success terms total			
141	Rame in	sucles, many lines			
222	Karris on	martial, brong mater			
	Name in	suchs, many lists			
24-	Kana an	mariat, from inst			
64.4	Name in	succes, many loans			
- #-	Name of	maria, home hate			
1.4.1	Name of	Starlah, Sound Padde			
14-	Name of	marias, mental fader			
(1)	Name or	searcher, manage fragment			
	Name on	one has been have			
244	Alanta in	sector, many lists			
 4. 	Frank in	analys, being frant			
14-1					
	fort ensure 1				

Figure 22-3 Arming Control

4. On the left panel, select a source type.

All the related areas will be listed and all the configured alarm rules of the selected source will be displayed. You can check the **Include Sub-Area** to display the alarm rules of sources in the child areas. If there are too many alarm rules, you can select a site or an area to display its alarm rules.

- **5. Optional:** If there are too many alarm rules, select a site or an area to display its alarm rules, or click \P to set conditions to filter alarm rules.
- 6. Check alarm rule(s) to perform the arming control.

IINote

- If the source is Alarm Input, an icon 🕐 will display if there is an exception. You can view the exception details by moving the cursor on the icon.
- The ignorance and acceptance settings in the Alarm Center only controls the alarm receiving on the current Control Client. But the disabling and enabling settings in the Alarm Center control the alarm receiving on the platform.

Ignore	a. Check alarm rule(s) in Accepted status.
Alarm	b. Click Ignore \rightarrow Ignore Alarm to open the ignorance settings panel.

- c. Set the start time, duration, or purpose of the ignorance.
- d. Click **Save** to ignore the selected alarm rule(s).

IINote

If you ignore an alarm rule, the current Control Client will not receive this alarm during the ignorance duration even though it is triggered.

For example, if you set the ignorance duration to one hour, the alarm cannot be received by the current Control Client, but will be recorded as a log on the platform within one hour. The alarm will be received again by the current Control Client after one hour.

Accept Alarm	 a. Check alarm rule(s) in Ignored status. b. Click Accept → Accept Alarm to accept the selected alarm rule(s).
	Note
	If you accept an alarm rule, the current Control Client will receive this alarm and you can view the alarm information on the current Control Client.
Disable Alarm	 a. Check alarm rule(s) in Enabled status. b. Click Ignore → Disable Alarm to open the settings panel. c. Set the start time, duration, or purpose of the disabling. d. Click Save to disable the selected alarm rule(s).
	I Note
	If you disable an alarm rule, the platform will not receive and record this alarm during the disabling duration even though it is triggered. For example, if you set the disabling duration to one hour, the alarm cannot be received and recorded by the platform within one hour. The alarm will be received again by the platform after one hour.
Enable Alarm	 a. Check alarm rule(s) in Disabled status. b. Click Accept → Enable Alarm to enable the selected alarm rule(s).
	Note
	If you enable an alarm rule, the platform will receive this alarm and you can view the alarm information on any client.

22.5 Event and Alarm Search

On the event & alarm search module, you can view the alarm overview, search the historical event or alarm, and search the evidence by setting search condition as required.

22.5.1 Alarm Overview

In the alarm overview module, it gives you an overview of the alarm distribution, top 5 alarms and top 5 warning zones.

In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Investigation \rightarrow Event & Alarm Search $\rightarrow \bigodot$ Overview to enter the Alarm Analysis page.



Figure 22-4 Alarm Analysis

You can click **Settings** in the upper-right corner to customize the event, alarm, or event and alarm types to be calculated in the overview page.

In the upper area of the page, the number of events triggered in the last 7 days or last 30 days are displayed in vertical bar chart.

In the lower-left area of the page, the top 5 alarms triggered in today, last 7 days or last 30 days are displayed in horizontal bar chart. The type of information displayed here will change according to the report target on the Settings pane. For example, if you select **Alarm** on the **Settings** pane as the report target, the Top 5 Alarms will only display data of the alarms. Click the number of an alarm to jump to the Event and Alarm Search page. Also, the **Trigger Alarm** field will also change according to your selection on the Settings pane.

In the lower-right area of the page, the top 5 areas with alarm in today, last 7 days or last 30 days are displayed in horizontal bar chart.

22.5.2 Search Event and Alarm Logs

You can search the event and alarm log files of the added resource for checking.

Before You Start

You should configure the event and alarm settings via Web Client. See User Manual of HikCentral Professional Web Client for details.

Steps

- In the top left corner of Control Client, select
 → All Modules → Investigation → Event & Alarm Search →
 Event & Alarm Search to enter the Event & Alarm Search page.
- 2. Set the time range for search.
 - Select a predefined time period for search.
 - Select Custom Time Interval and specify the start time and end time for search.
- 3. Select the event type as All, Not Trigger Alarm or Trigger Alarm.

All

Both events and alarms.

Not Trigger Alarm

The events happened but were not triggered as alarms.

Trigger Alarm

The events happened and were triggered as alarms.

4. Optional: If you select Trigger Alarm, you can set the following filter conditions.

Marking Status

Switch **Marking Status** on and select **Marked** or **Unmarked** to filter the marked or unmarked alarms/events.

Acknowledging Status

Switch **Acknowledging Status** on and select **Acknowledged** or **Unacknowledged** to filter the acknowledged or unacknowledged alarms/events.

Alarm Priority

Select the priority level to filter the alarms/events by priority.

Category

Select the category to filter the alarms/events by category.

- 5. Enable Area and then click [] to select the area of the source.
- 6. Enable Triggered By and then select the triggering events and source from the current site or Remote Sites.

IINote

The Remote Site is only available for the Central System with Remote Site Management module (based on the license you purchased).

- 7. Optional: If you select events of the Access Control category, enter the entered/exited person's name.
- **8. Optional:** If you have entered the additional information about the alarm on the third-party system, enter the additional information in the **Third-Party Additional Information** when searching for a third-party event or alarm.
- 9. Enable Event & Alarm Name to select the event/alarm name in the drop-down list.

10. Click Search.

The matched event or alarm logs display on the list.

11. Optional: Perform the following operation(s) after searching for alarms and events.

View Event or Alarm Details	Click the name of the searched event or alarm to view the details and the linked
Mark Event and Alarm	Click 🗈 to mark the event or alarm as desired. The color of the icon turns to 💌 .
Export Events and Alarms	Click 🗈 in the Operation column to export the specified event or alarm to the local PC. And you can view the exporting process in the Download Center by clicking 🖪 in the top of the page.
	Or click Export in the top right corner of the search result page and select the format as Excel , CVS , or PDF to export all searched events and alarms to the local PC.
	I Note
	When exporting all events and alarms in Excel format, you can check Include Picture Information to export the related pictures.
Switch to Auxiliary Screen	Click 🖻 to open the Alarm Search or Event Search page as a auxiliary screen. You can view the alarms or events on the auxiliary screen, as well as operating the other pages of the Control Client.

Chapter 23 Evidence Management Center

In the Evidence Management Center, you can manage evidence and the unlinked files (including pictures, videos, audios and other files), which contain important information about incidents such as traffic accidents and violent crimes in case of the need for settling disputes or legal cases.

23.1 Save Found Video Footage as Evidence

After searching for video footage under specific conditions, you can export the matched video footage which contains information of the incidents such as traffic accidents and violent crimes, and save it as evidence to the SFTP (Secure File Transfer Protocol) or local storage.

Before You Start

Make sure you have set the storage location to SFTP or local storage on the Web Client. For details, refer to the Evidence Management chapter in the User Manual of HikCentral Professional Web Client.

Steps

1. Search video footage.



For details, see Video Search .

- 2. Enter the Export pane.
 - On the video file list, click the time range to play back the video file, and then click 🔝 .
 - Select video file(s) from the video file list, and then click **Export** at the upper-right side.

Export		
File Information		
File Name	Download Time	6
1000	2021/10/24 19:	14:19 - 2021/10/24 19:14:20
line and	2021/10/24 19:	14:20 - 2021/10/24 19:14:52
100	2021/10/24 19:	15:38 - 2021/10/24 19:15:40
102100	2021/10/24 19:	16:58 - 2021/10/24 19:17:00
 AVI EXE 		
Merge Reco		
	otage of the same ca much size of the much	mera will be merged to one video ged file is 2 GB.
Save to Evidence	Management Center	t
Download V	SPlayer	
Save		

Figure 23-1 The Export Pane

- **3.** Select format for the saved video footage.
- **4. Optional:** Check **Merge Recorded Files** to merge the video footage of one camera into one video file.
- 5. Switch on Save to Evidence Management Center and then set the adding mode.

Add to Existing Evidence

Add the video file(s) to the existing evidence, which can be searched by the name or ID. After saving the video file(s) as evidence, you can see the video file in the Content of Evidence section on the evidence details panel.

Create Evidence

Set the parameters such as evidence ID, evidence type, evidence tag, on-site organization, result, and evidence status to create a new evidence.

INote

You can add and delete the evidence type, evidence tag, on-site organization, and result on the Web Client, see the Evidence Management chapter in the *User Manual of HikCentral Professional Web Client* for details.

Evidence Type

Select the type of accident or criminal incident recorded in the video file(s), such as theft, robbery, or attack.

Evidence Tag

Add one or more tag(s) for the evidence that needs following quick view and operation.

On-site Organization

The organization or personnel (e.g., police, fire department) on the site of the accident or criminal incident, which is responsible for collecting the evidence of the accident or criminal incident..

Result

The result or conclusion of the accident or criminal incident, such as arrested, warned, or injured.

Evidence Status

Select **Disable** if the related case is settled, and select **Enable** if the related-case is pending.

Only Upload File

Only add the video file(s) without saving it as evidence.

6. Optional: Check Download VSPlayer to download VSPlayer when exporting the video footage.

INote

This option is available when you select AVI or MP4 as the format.

7. Click Save to save the video file(s) as evidence.

The video file(s) will be downloaded in the Download Center, and then be uploaded as evidence to the SFTP or local storage.

IINote

- For details about the Download Center, see Manage Downloading Tasks .
- You can search the saved evidence. For details, see <u>Add Evidence</u>.

23.2 Save Manually Recorded Video as Evidence in Live View

During live view, you can manually record video footage which contains important information about incidents such as traffic accident and violent crimes, and save it as evidence to the SFTP (Secure File Transfer Protocol) or local storage.

Before You Start

Make sure you have set the storage location to SFTP or local storage on the Web Client. For details, refer to the Evidence Management chapter in the User Manual of HikCentral Professional Web Client.

Steps

1. Start live view.



See *Live View* for details.

2. Click in the toolbar of the display window to start the manual recording.

The icon turns to 🦲

3. Click 🛅 to stop recording.

A dialog will pop up.

- 4. Click Save as on the dialog to open the Save as panel.
- 5. Check Save to Evidence Management Center and then set the required information for the evidence.

iNote

For details about the required information for the evidence, see <u>Save Found Video Footage as</u> <u>Evidence</u>.

6. Click Save.

The saved recorded video footage will be uploaded to the SFTP or local storage.

IINote

You can search the saved evidence. For details, see $\underline{\textit{Add Evidence}}$.

23.3 Save Clipped Video as Evidence in Playback

During playback, you can manually clip video footage which contains important information about incidents such as traffic accident and violent crimes, and save it as evidence to the SFTP (Secure File Transfer Protocol) or local storage.

Before You Start

Make sure you have set the storage location to SFTP or local storage on the Web Client. For details, refer to the Evidence Management chapter in the User Manual of HikCentral Professional Web Client.

Steps

1. Start playback.

IINote

For details, see <u>Playback</u>.

Click to start clipping.
 The icon turns to .

3. Click to stop clipping.

A dialog will pop up.

- 4. Click Save as on the dialog to open the Save as panel.
- 5. Check Save to Evidence Management Center and then set the required information for the evidence.

JiNote

For details of the required information for the evidence, see <u>Save Found Video Footage as</u> <u>Evidence</u>.

6. Click Save.

The clipped video footage will be uploaded to the SFTP or local storage.

INote

You can search the saved evidence. For details, see $\underline{\textit{Add Evidence}}$.

23.4 Save Downloaded Video Footage as Evidence

When the downloading task is completed in the Download Center, you can save the downloaded video footage which contains important information about incidents such as traffic accidents and violent crimes, and save it as evidence to the SFTP (Secure File Transfer Protocol) or local storage.

Before You Start

Make sure you have set the storage location to SFTP or local storage on the Web Client. For details, refer to the Evidence Management chapter in the User Manual of HikCentral Professional Web Client.

Steps

iNote

For details about managing downloading tasks, see Manage Downloading Tasks .

- In the top left corner of the Client, select → All Modules → Management → Download Center .
- 2. Click Done to view the completed task.
- 3. Select the downloaded video footage and then click Save as to open the Save As panel.

4. Check **Save to Evidence Management Center** and then set the required information for the evidence.

IINote

For details about the required information for the evidence, see <u>Save Found Video Footage as</u> <u>Evidence</u>.

5. Click Save.

The saved video footage will be uploaded to the SFTP or local storage.

IINote

You can search the saved evidence. For details, see $\underline{\textit{Add Evidence}}$.

23.5 Add Evidence

You can add evidence about incidents such as traffic accidents and violent crimes in case of the need for settling disputes or legal cases. You can set detailed information for the added evidence, including the evidence name, ID, type, tag, on-site organization, result/conclusion, and status. Also, you can upload the file (including pictures, audios, videos, Excel file, CSV file, PDF file, and others) as the evidence content from cameras or local PC.

Before You Start

Make sure you have configured basic settings on the Web Client. For details, refer to the Evidence Management chapter in the User Manual of HikCentral Professional Web Client.

Steps

- 1. In the top left corner of the Client, select → All Modules → Evidence Management Center → Evidence .
- 2. Select Evidence Management on the left.
- **3.** Click **Add** to enter the Add Evidence page.

*Evidence Name	Evidence_20211103104132	
*Evidence ID		
Evidence Type	Other	4
Evidence Tag	+ Add Tag	
On-Site Organization	Other	3
Result	Other	89
Evidence Status	Enabled	9
Description		
		12
Adding Mode	Local Report Camera	
O Evidence Content	1 Uplead	

Figure 23-2 Add Evidence

4. Create a name for the evidence.

The evidence ID will be generated automatically on the Client. You can edit the evidence ID which should be 1 to 64 letters or digits.

- **5.** Set the type, tag, on-site organization, result/conclusion, status, or description for the evidence.
- 6. Optional: Set the mode of adding files as the evidence.
 - Select Local and click Upload to upload files (such as pictures, audios, and videos) from the local PC for the evidence content.
 - Select Camera, check cameras in the Linked Camera list, select the uploading mode, and set the corresponding parameters for the selected uploading mode. If you select Upload at Specified Time, you should specify the start time and end time of file uploading and recording. If you select Upload when Wi-Fi Detected, the files will be automatically uploaded

once the Wi-Fi is detected and connected, so you are only required to specify the start time and end time of file recording.

iNote

When the uploading mode is **Upload when Wi-Fi Detected**, only supports uploading evidence from cameras linked to the same device.

- 7. Finish adding the evidence.
 - Click Add to add the evidence and back to the Evidence Management page.
 - Click Add and Continue to save the settings and continue to add other evidence.
- **8. Optional:** Perform further operations after adding evidence(s) if needed.

Refresh Evidence	Click Refresh to refresh the latest view of evidence list.
View Details and Edit Evidence	Click the evidence name to view the details of evidence's basic information and operation record. You can also edit the basic information of the evidence, such as editing the evidence content, selecting the evidence type, and adding the evidence tag.
Delete Evidence	Select the evidence(s) and click Delete to delete the evidence(s).
Filter Evidence	Click ∇ on the upper right corner of the Evidence Management page, enter a keyword in the search box or set filter conditions, and click Filter to filter the target evidence.
Enable/Disable Evidence	Click Disable Evidence to disable the evidence if the related case is settled, or click Enable Evidence to enable the selected evidence if the related-case is pending.
Export Evidence Record	Click Export to export the selected evidence record(s) in the Excel, CSV, or PDF format.
Record	i Note
	You can check Include Evidence File to export the attached evidence file.

23.6 Manage Unlinked Files

The unlinked files refer to the files about incidents such as traffic accidents and violent crimes in case of the need for settling disputes or legal cases, but have not been linked with any evidence. You can manage the unlinked files, such as adding and viewing the files by category (pictures, videos, audios, and others). You can also link the added files with the specific evidence.

23.6.1 Add and View Unlinked Files

You can add the files which are unlinked with evidence(s). For the added unlinked file(s), you can perform more operations such as viewing the added files by category, filtering and exporting the unlinked files.

Steps

- In the top left corner of the Client, select → All Modules → Evidence Management Center → Evidence .
- 2. Select File Management on the left.




Figure 23-3 File Management Page

- 3. Click Add.
- **4.** Select the pictures, videos, audios, or other files from local PC to add.
- 5. Optional: Perform further operations if needed.

View the Unlinked Files by Category	At the top of File Management page, you can view the total number of unlinked files or the number of categorized files, including pictures, videos, audios, and others. You can also click each category to view all of the corresponding files information, including the file name and uploading time.
Filter the Unlinked Files	Click ∇ in the upper right corner to unfold the filter pane, enter the evidence name in the search box or select the creation time, and then click Filter to filter the target evidence.
Refresh the Unlinked Files	You can click Refresh to refresh the file list.
Floating Window Display	Hover your cursor on the added picture to view the enlarged picture in a floating window.
Link the Unlinked Files to Evidence	For details, refer to <u>Link Files with Evidence</u> .

Export the Unlinked Files	Select the unlinked file(s) and click Export to export the file(s).
	For viewing the file exporting records, refer to <u>Manage Operation</u> <u>Records</u> .
Delete the Unlinked Files	Select the unlinked file(s) and click Delete to delete the selected file(s).

23.6.2 Link Files with Evidence

You can link the added file with the existing evidence or newly added evidence. The linked files recorded in the evidence can be used as materials in case of the need for settling disputes or legal cases.

Before You Start

Make sure you have added the file(s). For details, refer to Add and View Unlinked Files .

Steps

- In the top left corner of the Client, select Select All Modules → Evidence Management Center →
 Evidence → File Management .
- 2. Select the unlinked file(s) in the list.
- **3.** Click **Link Evidence** to enter the Link Evidence pane.

Link Evidence	×
Linking Mode	
C Link Existing Evidence	
Create New Evidence	
Evidence Name *	
Evidence_20211103114515	
Evidence ID*	
Evidence Type	
Other	~
Evidence Tag	
+ Add Tag	
On-Site Organization	
Other	~
Result	
Other	×
Evidence Status	
Evidence Status Enabled	

Figure 23-4 Link Files with Evidence

4. Select the linking mode.

- Select Link Existing Evidence and enter the evidence name/ID/tag/description in the Select Evidence box to select the existing evidence for linking.
- Select **Create New Evidence** and create a new evidence for linking.

IINote

For details about adding evidence, refer to $\underline{\textit{Add Evidence}}$.

5. Click Save.

The linked files will not be displayed in the list.

23.7 Manage Operation Records

You can manage the evidence operation records, including viewing or deleting the upload/ download records of evidence or files from the local PC or cameras.

In the top left corner of the Client, select $\square \rightarrow$ All Modules \rightarrow Evidence Management Center \rightarrow Operation Record .

Upload Record

On the Upload Record page, you can view the records (including evidence or file size and upload status) of the evidence or files uploaded from local PC or related cameras.

You can also search for records by name, check a record and click \bigcirc / \odot / \odot in the Operation column to pause/start/retry the upload task. Or you can check record(s) and click **Delete** to delete the selected record(s).

Download Record

On the Download Record page, you can view the records ((including evidence or file size and download status) of exporting evidence or files on the platform.

You can also search for records by name, check a record and click \bigcirc / \bigcirc / \bigcirc in the Operation column to pause/start/retry the download task. Or you can check record(s) and click **Delete** to delete the selected record(s).

Chapter 24 Smart Wall

Smart wall provides security personnel with a larger overview of the regions they want to watch for any small or big unusual movement or activity. Large number of surveillance resources (such as cameras, maps) can be displayed on the smart wall for continuous monitoring. With the help of the Smart Wall, the security personnel can respond to the incidents effectively.

HikCentral Professional provides two modes of smart walls: Smart Wall (Decoding Device) and Smart Wall (Graphic Card).

In Smart Wall (Decoding Device) mode, the decoding devices can decode the streams and display the cameras' images on the display units connected to the decoding devices.

In Smart Wall (Graphic Card) mode, the graphic card of the PC running the Control Client will decode the images and other contents (such as pages of the Control Client) and display on the screens connected to the PC.

24.1 Manage Smart Wall (Decoding Device)

A Smart Wall (Decoding Device) is a special multi-monitor setup that consists of multiple monitors, screens or display units tiled together contiguously or overlapped in order to form one large screen, so that you can get a complete overview of large surveillance centers. With the smart wall, you can easily create views defining window division and content for the managed smart wall. What's more, the video triggered by event can also be displayed on smart wall to help operator quickly focus on the most critical matters. For example, if a door is opened, the smart wall can be configured to display the video of the camera nearest to the door.

This type of smart wall is mainly used in medium and large surveillance scenarios, such as surveillance center. In these scenarios, more than four display units are required to display the images.



Figure 24-1 Application Scenario: Smart Wall (Decoding Device)

Before decoding and display, you need to add decoding devices (such as video wall controllers and decoders) to the system, and create virtual smart walls via the Web Client. Then you need to link the decoding devices' decoding output to the windows of the virtual smart wall.

After the above configuration, the Control Client supports displaying camera's video on the smart wall to get a complete and clear overview of the videos.

In the top left corner of Home page, select $\blacksquare \rightarrow All Modules \rightarrow Tool \rightarrow Smart Wall$ to open the Smart Wall (Decoding Device) module.

			1000		
andi Anti		 2-1	19 . B	uci 🚥 🖮	
100					

Figure 24-2 Smart Walls

Click with the smart wall remotely.

The following icons are available on the Smart Wall window.

IINote

- The icons displayed vary with the capability of smart walls.
- You can select a widow and press the F2 key to set the camera No., and click **Confirm**. The camera No. will be displayed on the window.

lcon	Description
μ	When the smart wall settings on the SYS server are changed (e.g., more smart walls are added, linked decoding outputs are changed, decoding devices are deleted), a red dot will appear on this icon. Click it to synchronize the smart wall information.
(\Box)	Set to display the window No. on the smart wall, or view the details of the smart wall.
8/1	Unlock or lock the window. When you lock the window, you cannot display the video on this window or stop decoding and displaying on the window.
	Set the window division for the selected display window of smart wall. Double-click on the split window to enlarge the window.
\$ /\$	Display or hide the VCA rules on the display window of smart wall, such as configured target detection frames for VCA event.
	Stop all the windows' playing.

(D)	
	Save the current settings to the view or to other view. In this way, you can easily view the required live videos on the smart wall by calling this view.
	Note
	For details, refer to <u>View Settings</u> .
	Click 🔜 to view the view schedule of the current smart wall. You can change the schedule as needed.
	Note
	For details about how to define the schedule, refer to <u>Set Schedule for Displaying</u> <u>Views on Smart Wall</u> .
⊞}	Create a roaming window to open a virtual window on the screen(s).
	Click 🔤 and drag the cursor to select windows to be joined. Click 国 and the joined windows will be split.
	Open a window by setting coordinates, height, and width.
\Box / \Box	The client will display or hide the images the same as those on the smart wall.
	Add a text window to enter texts as needed.
0	Add a window to display the time whose format can be customized.
	Show or hide the text window or clock window.
	 Set the layout template via the following operations and click Save to save settings. Select a window division mode. Select the position of the text and set corresponding pixel value to adjust the size of the text.
	Enable Open Window to enable the function for opening windows.
毘	Select a screen to display the desktop.
不/业	Top the window or set the window to the bottom.
	Select a logo for the window.
*	Switch the stream type of the video.
	Zoom in the window.
2	Start to use the PTZ control.
	Stop decoding.
Ð	View playback.

lcon	Description
83	View the decoding status.
Ľ	Open the preview window.

24.1.1 Decode and Display Directly

After setting the smart wall via Web Client, the video streams from the camera can be decoded by the configured decoding outputs, and then you can display the decoded videos on the smart wall.

Before You Start

Add the smart wall via Web Client. For details, refer to User Manual of HikCentral Professional Web Client.

Steps

- In the top left corner of Control Client, select
 → All Modules → Tool → Smart Wall to enter the Smart Wall page.
- 2. Select a smart wall.
- **3.** Click I in the upper-right corner of the smart wall window to select a window division mode.
- **4.** Display resources on smart wall.
 - Display Signal Source on Smart Wall: Click Device Signal Source on the left panel. Select a signal source from the drop-down list, and drag the signal source to display window of the smart wall.
 - Display Camera on Smart Wall: Click Network Signal Source on the left panel. Select a camera from the drop-down list, and double-click a camera name or drag the camera to the layout area of smart wall to display the camera on the smart wall.

IINote

- You can hover the cursor over a resource, click , and select **Crop Signal Source** to adjust the resolution.
- You can hover the cursor over a resource, click and select Add to Group to add the resource to other groups.
- You can view live view of devices in thumbnail mode at the bottom of the page.
- It is only available for the central system with Remote Site Management module (based on the license you purchased).
- Batch Display Cameras on Smart Wall: Click Network Signal Source on the left panel. Hold the Ctrl key and select multiple cameras in an area or different areas, and then drag them to the layout area of smart wall and click Play in Batch to display multiple cameras on the smart wall in a batch.
- Display Area on Smart Wall: Click Network Signal Source on the left panel. Select a site from the drop-down list, and double-click the area or drag the area to the layout area of smart wall to display the resources in the area on the smart wall.

iNote

If there are multiple resources in the area, when you drag it to the layout area of smart wall, you need to select **Play in Batch**, **Single-Window Auto-Switch**, or **Multi-Window Auto-Switch**to display each resource in one display window or display area auto-switch in one or more display windows on the smart wall. For more details about area auto-switch, refer to *Auto-Switch Cameras in One Window*.

- Display View on Smart Wall: Click and the left , and double-click the view name to display on smart wall.



Figure 24-3 Display Live Video on Smart Wall

The decoded video stream is displayed on the smart wall.

5. Optional: Select a display window which is linked with the camera to display the live video on the large window at the bottom of the page, and then perform the following operation(s).

View Camera Status	Click 🜆 to show the camera's frame rate, resolution, and stream format.
Switch Stream	On the Web Client, you can set the default stream type of the live video of the cameras displaying on the smart wall. If you want to change the stream, such as changing to main stream to get better image quality, you can switch stream manually as follows.
	Click or to switch the live view stream to main stream, sub-stream, or smooth stream.
	Note
	Smooth stream needs to be supported by device.
Enable PTZ Control	Click Market to enable PTZ (pan, tilt, zoom) control function on the display window. And then you can control PTZ and set preset, patrol, and pattern. See PTZ Control for details.
Switch to Playback	Click 🛐 to switch to playback mode. For details, refer to Play Video File .

Stop Decoding and Displaying

Click or we to stop the decoding and displaying for the specified window or all windows.

IINote

For the locked windows and alarm linked windows, you cannot stop the decoding and displaying.

24.1.2 View Settings

You can set the view and organize the views into a group for displaying the video on smart wall conveniently. You can also perform the view auto-switch for the view group on the smart wall.

Add View Group

With view group, you can group the related views together for ease of viewing and management. For example, all the views of building A can be placed in one view group to reflect their relationships in the real world.

Steps

- 1. In the top left corner of Control Client, select → All Modules → Tool → Smart Wall to enter the Smart Wall page.
- 2. Click 🔢 to open the View window.
- 3. Select Public View or Private View to add this view group.

IINote

- The view groups and views belonging to the public view can be seen by all the system users.
- The view groups and views belonging to the private view can only be seen by the user who has added it.
- 4. Click 📰 to open Add View Group window.
- 5. Edit the group name or use the default one.
- 6. Click Save to add the group.
- 7. Optional: Perform the following operation(s) after adding the view group.

Edit View Group	Select the view group, click 🔤 , and click Edit to edit the view group
	name.

Delete View Group Select the view group, click , and click **Delete** to delete the group.

Add View

View defines which cameras are displayed on the monitors of the smart wall. In this way, you can quickly access the frequently used cameras on smart wall for an excellent overview.

Steps

- In the top left corner of Control Client, select → All Modules → Tool → Smart Wall to enter the Smart Wall page.
- 2. Display the videos of cameras on the smart wall.

INote

For more details, refer to **Decode and Display Directly** .

- 3. Click 🔝 to open the View window.
- **4.** Select a view group.
- 5. Click + to open Add View window.
- 6. Enter the view name or use the default one.
- **7. Optional:** Set **Schedule Play** switch to on and set when to automatically display the view on smart wall.

IINote

For more details about how to set view schedule, refer to <u>Set Schedule for Displaying Views on</u> <u>Smart Wall</u>.

8. Click Save to save the view.

Hover the cursor over the view name to view the thumbnail of the view.

9. Optional: Perform the following operation(s) after adding the view.

Start Decoding and Displaying	Double-click the view to start decoding and displaying on smart wall conveniently.
Edit View	Select the view group, click 🔤 , and click Edit to edit the view name.
Delete View	Select the view group, click in , and click Delete to delete the view.

Set Schedule for Displaying Views on Smart Wall

The view schedule is used to define when to automatically display the view on smart wall. According to the schedule, the view will play on the smart wall at the time point(s) or the fixed time point(s) on regular date(s) in one week repeatedly.

When adding a view, enable Scheduled Play and do one of the followings:

- Check **Repeated Play**, select the days in one week, and set a regular time for displaying the view on smart wall.
- Uncheck **Repeated Play**, and set a specific time for displaying the view on smart wall.

ew2021			
eduled Pla			
Repeated	Play		
MON	TUE	WED	THU
FRI	SAT	SUN	
00:00	÷		
1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1			

Figure 24-4 Set Schedule

Click $\overrightarrow{\mathbf{m}}$ to view the view schedules of the current smart wall. You can hover the cursor on the view name and click $\overrightarrow{\mathbf{m}} \rightarrow \mathbf{Delete} \ \mathbf{Plan}$ or $\mathbf{Delete} \ \mathbf{Week} \ \mathbf{Plan}$ to delete the plan of a day or a week.

24.1.3 Set View Auto-Switch Interval

View auto-switch is used for displaying the views of a view group one after the other. You can specify the interval between view changes.

Before You Start

Add at least two views into one view group, see <u>Add View</u> for details.

Steps

- In the top left corner of Control Client, select
 → All Modules → Tool → Smart Wall to enter the Smart Wall page.
- 2. Click 🔢 to open the View window.
- **3.** Click << or >> in the toolbar of the video view to set the auto-switch interval.

IINote

Setting the auto-switch interval for the view group is not supported.

24.1.4 Auto-Switch Cameras in One Window

Auto-switch in one window is used for displaying the videos from the cameras in an area or different areas, one after another, in a single window. You can specify the interval between camera changes.

Steps

- 1. In the top left corner of Control Client, select
 → All Modules → Tool → Smart Wall to enter the Smart Wall page.
- 2. Click Network Signal Source on the left panel to enter the Camera page.
- **3.** Select area or cameras for auto-switch.
 - Drag an area on the left panel to the window linked with a decoding output.

IINote

Make sure the cameras have been added to the area. See User Manual of HikCentral Professional Web Client.

- Hold the Ctrl key and select multiple cameras in an area or different areas, and then drag them to the window linked with a decoding output.

IINote

Up to 32 cameras can be selected for auto-switch in one window.

4. Click **Single-Window Auto-Switch** in the pop-up menu to display the videos of the cameras in one display window of the smart wall.

The cameras starts switching automatically on the smart wall.

- **5. Optional:** Click << or >> in the toolbar of the video view to set the auto-switch interval.
- 6. Optional: Click 🛅 and perform the following operations.

Set Auto-Switch Interval	In Auto-Switch Interval, select an interval in the drop-down list to set the interval.
Set Stream Type	 In Stream Type column, select a stream type from the drop-down list for a specific resource. Click Set Stream Type to set the stream type for all the added resources.
Add Resource for Auto-Switch	Click Add to select resources to be added.
Delete the Added Resource	Check the resource(s) and click Delete to delete the selected resource(s).
Adjust Resource Order	Click Up or Down to adjust the display order of the resource(s).

Edit Auto-Switch Click ∠ to edit the window for auto-switch. Window

24.1.5 Auto-Switch Cameras in Multiple Windows

Auto-switch in multiple windows is used for displaying the videos from the cameras in an area or different areas, one after another, in multiple windows. You can specify the interval between camera changes.

Steps

- 1. In the top left corner of Control Client, select → All Modules → Tool → Smart Wall to enter the Smart Wall page.
- 2. Click Network Signal Source on the left panel to enter the Camera page.
- **3.** Select an area or cameras for auto-switch.
 - Drag an area on the left panel to the window linked with a decoding output.

INote

Make sure the cameras have been added to the area. See User Manual of HikCentral Professional Web Client.

- Hold the Ctrl key and select multiple cameras in an area or different areas, and then drag them to the window linked with a decoding output.

INote

Up to 32 cameras can be selected for auto-switch in one window.

4. Click **Multi-Window Auto-Switch** in the pop-up menu to display the videos of the cameras in multiple display windows of the smart wall.

The cameras start switching automatically on the smart wall.

- 5. Optional: Click << or >> in the toolbar of the video view to set the auto-switch interval.
- 6. Optional: Click i and perform the following operations.

Set Auto-Switch Interval	In Auto-Switch Interval, select an interval in the drop-down list to set the interval.
Set Stream Type	 In Stream Type column, select a stream type from the drop-down list for a specific resource. Click Set Stream Type to set the stream type for all the added resources.
Add Resource for Auto-Switch	Click Add to select resources to be added.
Delete the Added Resource	Check the resource(s) and click Delete to delete the selected resource(s).
Adjust Resource Order	Click Up or Down to adjust the display order of the resource(s).

Edit Auto-Switch Click ∠ to edit the window for auto-switch. Window

24.1.6 Create a Roaming Window

Windowing is to open a virtual window on the screen(s). The window can be within a screen or span multiple screens. You can move the window on the valid screens as desired and this function is called roaming. With windowing and roaming function, you can create custom window and the window size and position will not be limited by the actual screen(s).

Steps

- 1. In the top left corner of Control Client, select
 → All Modules → Tool → Smart Wall to enter the Smart Wall page.
- 2. Click and drag on the screens which are linked to decoding outputs to open a window.

iNote

- Screens linked to BNC outputs are not available for opening a window.
- You can also click must to open a window by setting coordinates, height, and width.



Figure 24-5 Open a Window

3. Optional: Perform the following operation(s) after opening a window.

Roam Click on the window and hold the mouse to move the window within the scope of the valid screens.

Adjust Window Size	Move your cursor to the window edges and adjust the window size when the cursor becomes a directional arrow.
Enlarge Window	Double-click the window and it will be enlarged to fill the spanned screens and display on the top layer. Double-click again to restore.
Stick Window on Top	Click 🚮 display the window on the top layer.
Stick Window at Bottom	Click 🔛 display the window on the bottom layer.

24.1.7 View Alarm's Related Video on Smart Wall

If you have enabled the smart wall linkage for an alarm, the live view of cameras or public views related to the alarm will pop up on the chosen smart wall when the alarm is triggered. Therefore, you will know alarm details in a timely manner for further operations.

- When an alarm linked with multiple cameras in one display window is triggered, the window will be divided into an adaptive division mode and show the videos of all cameras.
- When multiple alarms linked with one display window are triggered, the window will be divided into an adaptive division mode and show the alarms' related videos.
- When each alarm linked with multiple display windows is triggered, every window will show one alarm's related video. If the alarms exceed the window limit, the window will be divided into an adaptive division mode and show the more alarms' related videos.

For example, there are alarm A, alarm B, alarm C and alarm D are linked with window 1, window 2 and window 3 of smart wall. When alarm A, alarm B, and alarm C are triggered, the display window of smart wall will show as the left figure below. When alarm D is also triggered, the display window will show as the right figure below.

Alarm A Window 1	Alarm B Window 2	1	Alarm D dow 1	Alarm B Window 2
Alarm C Window 3		-•	rm C dow 3	

Figure 24-6 Multiple Alarms Displayed on Smart Wall

JiNote

The alarm rules of the alarms displayed in the windows will not be changed when the window division mode changes.

24.1.8 View and Export Window No. and Camera ID

When displaying live view on smart wall, you can use a keyboard for convenient operations such as starting live view on smart wall, PTZ control, etc. If you want to display certain camera's live view in certain window on the smart wall, you should press the camera's identifier number and target window number on the keyboard, which are called **Camera ID** and **Window No**.

In the Web Client, you can set a unique ID for each camera added in the system. For details, refer to User Manual of HikCentral Professional Web Client.

In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Tool \rightarrow Smart Wall to enter the Smart Wall page, and click $\blacksquare \rightarrow$ Window No. & Camera ID \rightarrow Display Window No. to show the number of each window.

If you want to export a document which contains the IDs of all the cameras and smart wall information (such as smart wall name, row and column, etc.) as a reference, click **■** → **Window No. & Camera ID** → **View Window No. and Camera ID** to generate a document.

Click **Download** to download this document and save it in local PC. You can print it if necessary.

1 C 1	Contract of	
	1	
	1.10	
		Note
1.00	1000	INULE

- The exported file is in PDF format.
- The exported document also contains smart wall No., which are used for selecting smart wall via network keyboard.

24.2 Manage Smart Wall (Graphic Card)

Smart Wall (Graphic Card) is hardware independent. It doesn't require any decoding resources such as video wall controllers or decoders. The PC running the client can decode the streams by its graphic card and then display the content on the screens connected to the PC. As a result, it is cost efficient solution and easy deployment.

This type of smart wall is mainly used in small surveillance scenarios, such as supermarket, with less than four display units required.



Figure 24-7 Application Scenario: Smart Wall (Graphic Card)

In this smart wall mode, you can display not only the camera's videos on the smart wall, but also other display contents such as maps, health status, Monitoring page, etc.

IINote

Up to four screens are supported as smart walls for one Control Client in this mode.

24.2.1 Display Contents on Smart Wall in Smart Wall Mode

A variety of contents (e.g., video, map, face comparison) can be shared on the smart wall to help you respond quickly and effectively. The smart wall (graphic card) mode provides a convenient way to set up initial smart wall, check complete overview of the smart wall layout, or adjust the layout of the smart wall. You can select the desired smart screen and enter this mode to set window division, adjust layout, display contents on smart wall or perform other operations.

Before You Start

Make sure you have enabled GPU Hardware Decoding function in System \rightarrow Video \rightarrow Display .

Steps

1. In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Monitoring .

2. Click **ESS Smart Wall** on the left to enter smart wall page.

3. Enter Smart Wall Mode.

- Double-click a smart wall in the smart wall list.
- Drag a smart wall from the smart wall list to the layout area of smart wall.

- **4. Optional:** Click **1** at the top to choose the predefined window division to layout the display window of the smart wall.
- 5. In smart wall mode, display contents on the smart wall.
 - Display Camera on Smart Wall: Double-click a camera name or drag the camera to the layout area of smart wall area to display the camera on the smart wall.
 - Display Map on Smart Wall: Double-click the map or drag the map to the layout area of smart wall to display the map on the smart wall.
 - Display Area on Smart Wall: Double-click the area or drag the area to the layout area of smart wall to display the resources in the area on the smart wall.

IINote

If there are multiple resources in the area, when you drag it to the layout area of smart wall, you need to select **Play in Batch** or **Single-Window Auto-Switch/Multi-Window Auto Switch** to display each resource in one display window or display area auto-switch in one/multiple display window on the smart wall.

- Display View on Smart Wall: Drag the view to the layout area of smart wall and select **Single-Screen Auto-Switch** or **Replace Current View** to display the auto-switch view in one display window or replace current display content on smart wall.
- Display View Group on Smart Wall: Drag the view group to the layout area of smart wall to display auto-switch of each view in one display window on smart wall.
- Display Face Comparison on Smart Wall: Double-click the face comparison group or drag it to the layout area of smart wall to display the face comparison result on the smart wall.

6. Optional: In smart wall (graphic card) mode, perform one of the following operations.

View Resource Channel	You can view all resource channels displayed on smart wall.
Adjust Display Window	Drag one display window to another to adjust the layout order on smart wall.
Edit Name	Click — and select Edit Name to edit the name of the smart wall.
Show Smart Wall	Click — and select Show Smart Wall to show the name on the smart wall.
Display or Do Not Display Alarm on Screen	Click 🔜 to disable alarm display on the corresponding screen when an alarm is triggered. Click 🔛 to restore alarm display on the screen.
Exit Smart Wall Mode	Click Exit Smart Wall Mode to exit the mode.

24.2.2 Display Contents on Smart Wall in Live View Mode

During live view, if you see something important in the live view window, for example, a suspect caught by one camera or a VIP matched in the face comparison panel, you can display these contents on the smart wall to get a complete and larger overview.

After displaying the live contents on the smart wall (on another display) in this mode, you can continue view other live content, or perform other operations on the Control Client on the current display, without changing the content that smart wall displays. This function lets you keep an eye on your smart wall while working in Control Client. For example, the smart wall continues to show the current video while you start playback of this camera on the Control Client.

Display All Contents in Live View on Smart Wall

In the Monitoring module, you can display all contents you are viewing in the displaying windows onto the smart wall (graphic card) to get a larger overview by a one-touch operation.

IINote

Make sure you have enabled GPU Hardware Decoding function in System → Video → Display .

After starting live view, click a in the upper-right corner on the Control Client and select a smart wall to display all the displaying windows on the smart wall.



Figure 24-8 Display All Contents in Live View on Smart Wall

iNote

The contents include all the resources displayed in the display area, such as video of the cameras, maps, face comparison groups, access points, etc.

Hover the cursor on the top the displaying smart wall screen and click **Exit Smart Wall Mode** to stop displaying the contents on smart wall.

Display Camera on Smart Wall

You can display the live view of a camera on the smart wall without decoding, so as to show details of the monitored area of the camera in a timely manner.

Before You Start

- Connect your PC to at least one smart wall.
- Make sure you have enabled GPU Hardware Decoding function in System → Video → Display .

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Monitoring.
- 2. Optional: Click 🔳 to select a window division mode.
- 3. Display the live view of a camera on smart wall.
 - Hover the cursor on a live view window, click **m** in the window's toolbar, and then select a smart wall.

Note

You can also click **Smart Wall (Decoding Device)** to decode and display this camera on smart wall.

- Hover the cursor on a camera's name, click , and then hover the cursor on Display on Smart Wall to select a smart wall.
- **4. Optional:** Use a USB keyboard (such as DS-1005KI) to start live view of a certain camera on smart wall by pressing the camera's identifier number.

IINote

In the Web Client, you can set a unique ID for each camera added in the system. For details, refer to *User Manual of HikCentral Professional Web Client*.

Display Area on Smart Wall

You can display all the cameras' live view in an area on the smart wall to view the details in an area in a timely manner for an overview of the area.

Before You Start

- Connect your PC to at least one smart wall.
- Make sure you have enabled GPU Hardware Decoding function in System → Video → Display .

Steps

1. In the top left corner of Control Client, select $\blacksquare \rightarrow All Modules \rightarrow Surveillance \rightarrow Monitoring$.

Hover the cursor on an area's name, click in , and then hover the cursor on Display on Smart Wall to select a smart wall to display all cameras in the area on the smart wall.

Display Map on Smart Wall

You can display e-map and GIS map on smart wall to show the overall layout and locations of the added devices, or devices of a certain type. The alarm information will be displayed on the smart wall as well when an alarm is triggered.

Before You Start

- Configure a GIS map or e-map via the Web Client beforehand. For details, see User Manual of HikCentral Professional Web Client.
- Make sure you have enabled GPU Hardware Decoding function in System → Video → Display.

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Surveillance \rightarrow Monitoring .
- 2. Optional: Click 🔳 to select a window division mode.
- 3. Display a map on smart wall.
 - Hover the cursor on Map, click , and then move the cursor on Display on Smart Wall to select a smart wall.
 - Double-click **Map** to display it on the right panel. Click is in the upper-right corner of the map-displaying window and select a smart wall.

IINote

The devices added to the map will be displayed with the map.

Display View on Smart Wall

If you have saved a view, you can display it on smart wall in a timely manner with the saved window division and the correspondence between cameras and windows.

Before You Start

Save at least a view beforehand. For details, see Manage View .

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow All Modules \rightarrow Surveillance \rightarrow Monitoring$.
- 2. Click 📰 to open the View panel.
- **3.** Hover the cursor on a view name, click , and then hover the cursor on **Display on Smart Wall** to select a smart wall.

The view will be displayed on the selected smart wall in the saved window division mode.

24.2.3 Display Alarm's Related Video on Smart Wall

If you have enabled the smart wall linkage for an alarm, the live view of cameras or public views related to the alarm will pop up on the chosen smart wall when the alarm is triggered. Therefore, you will know alarm details in a timely manner for further operations. You can also manually display live view of one of the alarm-related cameras on the smart wall.

Before You Start

- Configure an alarm (and enable smart wall linkage for it) via the Web Client beforehand. For details, see *User Manual of HikCentral Professional Web Client*.
- Make sure you have enabled GPU Hardware Decoding function in System → Video → Display .

Steps

In the top left corner of Control Client, select ■ → All Modules → Surveillance → Alarm Center to enter the Alarm Center module.

The information of triggered alarms will be displayed.

- **2. Optional:** Click an alarm to display the live view of the alarm in the Related Video & Picture window in the lower-left corner of the client for a preview.
- 3. Display live view of a camera related to an alarm on smart wall.




Figure 24-9 Display Alarm's Related Video on Smart Wall

If you are viewing the camera's video in the Related Video & Picture window, click **Display Alarm on Smart Wall** under the window to select a smart wall.

- **4. Optional:** Hover the cursor on the top of the displaying smart wall to show the Exit Smart Wall Mode bar, and then click **a** to enable automatic alarm-video display on the current wall.
 - The icon sturns to sturns to sturns to sturn and the related cameras or views of the alarms configured with smart wall linkage can be displayed on the smart wall automatically when triggered.



Figure 24-10 Exit Smart Wall Mode Bar

• If you have disabled automatic alarm-video display on the current wall, the smart wall name will turn to (Alarm Disabled)Smart Wall Name.



Figure 24-11 Smart Wall Name with Alarm Disabled

IINote

This configuration won't be changed after restarting the Control Client.

- 5. Select → All Modules → Surveillance → Monitoring → Smart Wall , and then doubleclick the working smart wall's name to enter the Smart Wall Mode on the client.
 - The windows of the alarm-related cameras will be displayed in the right panel with a red title bar in tile mode with every camera's name showing in the respective windows.



Figure 24-12 Display Alarm on Smart Wall

- For alarm-related view, the view will be displayed in the right panel covering the images you are currently viewing in the saved window division mode.
- 6. Optional: Perform the following operations if you need.

View Alarm Details	Click a red title bar on the client to open the alarm information window for details.
Switch to Auto- Switching Mode	Click ≓ to switch between tile mode and auto-switching mode for the alarm-related cameras.

IINote

- In auto-switching mode, you can hover the cursor on the displaying window to perform operations including stream switching, switching between instant playback and live view, recording, camera switching, fast forward and slow forward.
- Up to 64 windows can be displayed on the smart wall. You can perform the above-mentioned tasks to control the live view displaying of the cameras and views.

- If you have enabled alarm on the smart wall, live view of alarms with higher priority will cover that of alarms with lower priority before the due time of smart wall displaying.
- You can configure the due time of smart wall displaying via the Web Client. For details, see User Manual of HikCentral Professional Web Client.
- When multiple alarms with the same camera/view linkage are triggered, the alarms will be displayed on smart wall showing alarm number. When new alarm with the camera/view linkage is triggered, the number will change. The alarm window title shows the alarm's name with the highest priority. Hover your cursor on alarm name, you can view all alarms in time and priority order and handle them in a batch.




Figure 24-13 Display Multiple Alarms with Same Camera/View Linkage on Smart Wall

24.2.4 Display Health Monitoring Page on Smart Wall

You can display the health monitoring page on smart wall for an overview status of the added devices and HikCentral Professional Service.

Before You Start

Add devices to HikCentral Professional via the Web Client. For details, see User Manual of HikCentral Professional Web Client.

Steps

 In the top left corner of Control Client, select → All Modules → Maintenance → Health Monitoring to enter the Health Monitoring module.

The overview status of the added devices and HikCentral Professional Service will be displayed.

2. Click 🔜 in the upper-right corner of the client and select a smart wall to display the health monitoring page on smart wall.




Figure 24-14 Display Health Monitoring Page on Smart Wall

3. Optional: Click **Exit Smart Wall Mode** on smart wall to stop displaying the health monitoring page on smart wall.

24.2.5 Display Desktop on Smart Wall

For certain scenarios, you can share the contents of your desktop on the smart wall for better display and experience. You can add the PC running RSC server to HikCentral Professional, and display that on smart wall like a normal camera.

Steps

1. Install the RSC server in local PC, and set the password for RSC server.



You can contact our technical support to get the installation package of RSC Server.

A Caution

The password strength of the device can be automatically checked. We highly recommend you change the password of your own choosing (using a minimum of 8 characters, including at least three kinds of following categories: upper case letters, lower case letters, numbers, and special characters) in order to increase the security of your product. And we recommend you change

your password regularly, especially in the high security system, changing the password monthly or weekly can better protect your product.

Proper configuration of all passwords and other security settings is the responsibility of the installer and/or end-user.

2. Enter Encoding Device Management page of Web Client to add the PC (regarded as an encoding device) running RSC server to HikCentral Professional by IP address.

IINote

When adding the PC to HikCentral Professional, the default port number is 8000, and the password should be the same with the one configured on RSC server in Step 1.

3. Optional: Configure related settings on Web Client if required, such as adding the virtual camera of PC to area, configuring recording, setting streaming server, etc.

IINote

- After adding virtual camera of PC to area, you can perform basic operations as the same with the normal cameras.
- If you want to record the video for the desktop displayed on the smart wall, you need to configure recording parameters for the virtual camera, and you cannot select encoding device as storage location.
- The virtual camera of PC is not calculated as the camera number of the license you purchased.
- 5. Display your desktop on smart wall.
 - Enter **Smart Wall Mode**, and double-click the name of virtual camera of PC or drag the virtual camera of PC to the layout area of smart wall area to display the desktop on the smart wall.

IINote

For more details about how to enter **Smart Wall Mode**, refer to <u>*Display Contents on Smart*</u> <u>*Wall in Smart Wall Mode*</u>.

Click Logical Resource tab, and hover the cursor on the name of virtual camera of PC. Then you can click → Display on Smart Wall and select a smart wall to display the desktop on the smart wall.

The virtual camera's icon will turn to 🚱 , and your desktop will be displayed on the smart wall.

Chapter 25 Broadcast

On the Control Client, you can broadcast to the devices or speaker units which have been added to the Web Client. After broadcasting, you can search for the broadcast records.

25.1 Broadcast to Connected Speaker Unit

You can broadcast to the connected speaker unit(s) by selecting the specific speaker unit(s) and the broadcast mode. The corresponding audio file or the user's voice will broadcast on the speaker unit(s) in real time.

Before You Start

- Make sure you have grouped speaker units on the Web Client.
- Make sure you have added speaker unit(s) to area(s) on the Web Client.
- Make sure you have added media file(s) to the media library on the Web Client.
- For details about the above operations, refer to the User Manual of HikCentral Professional Web Client.

Steps

- 1. In the top left corner of Control Client, select in the top left corner of Control Client, select window.
- 2. Click By Speaker Unit on the top of the window.
- **3.** Select the speaker unit(s) for broadcast.

IINote

You should select the online speaker unit(s).

- Check Group, and select one or more speaker units from speaker unit group(s).

iNote

You can click **Display Speaker Units Not Grouped** to display the speaker unit(s) that are not grouped.

- Check **Area**, and select one or more speaker units from the area(s) where the speaker units are added.
- **4.** Select the broadcast mode.
 - Check Speak.
 - Check Play Audio, and select an audio file from the media library.

iNote

You can click **Download** to download and play the selected audio file beforehand to ensure the audio will broadcast fluently and correctly.

5. Click Start.

What to do next

Speak to the PC microphone or play the audio file.

25.2 Broadcast to Connected Devices

Perform the broadcast function to distribute audio content to the added device if the device has an audio output.

IINote

- Make sure the PC has available microphone for broadcasting audio to the device.
- If the client is performing two-way audio with the device's camera, you cannot start broadcasting with the device, and vice versa.
- The Cloud P2P device supports broadcasting if it enables DDNS.
- a. In the top left corner of Control Client, select $\blacksquare \rightarrow$ Tool \rightarrow Broadcasting \rightarrow By Device .
- b. Select an existing device group or click 🖿 to add a device group if needed, and then click Add to select the device(s) to broadcast to.
- c. Start or stop broadcasting.

Start All	Click Start All to start broadcasting to the selected device(s).
	Note
	You can view the real-time broadcast status.
Stop All	Click Stop All to stop broadcasting to the selected device(s).

25.3 Search for Live Broadcast Records

You can set search conditions including the start time, end time, and the broadcaster to search for live broadcast records.

Before You Start

Make sure you have finished live broadcast. Refer to <u>Broadcast to Connected Speaker Unit</u> for details.

Steps

- In the top left corner of the Home page, select
 → All Modules → Investigation → Live Broadcast and Recording .
- **2.** Set the start time.
- 3. Set the end time.
- 4. Select a broadcaster from the drop-down list.
- 5. Click Search.

You can view the search results on the right side and view the details of each record, including the broadcaster, the number of the speaker units, the start time, and the file size.

6. Optional: Perform the following operations.

Download	Click 🚡 in the Operation column to download the broadcasted audio.
View Speaker Unit	Click > _ to view the speaker unit.

Chapter 26 Intelligent Analysis Report

Reports, created for a specified period, are essential documents, which are used to check whether a business runs smoothly and effectively. In HikCentral Professional, reports can be generated daily, weekly, monthly, annually, and by custom time period. The reports can also be added to the dashboard for browsing at a glance. You can use reports as basis in creating decisions, addressing problems, checking tendency and comparison, etc.

26.1 Customize Report Dashboard

The report dashboard provides an at-a-glance view for the reports supported by the system, such as people counting report, vehicle analysis report, and queue analysis report. You can customize the report dashboard as required.

Steps

- In the top left corner of the Client, select All Modules → Intelligent Analysis → Intelligent Analysis Overview .
- **2. Optional:** Click $\lor \rightarrow$ **Add Dashboard** on the report dashboard page to add a new dashboard.

iNote

You can add up to 100 dashboards.

The new dashboard appears and it is named as "Dashboard + The Time When It was Added" by default. For example, in "Dashboard20190916102436", "2019" represents year, "09" month, "16" date, "10" hour, "24" minute, and "26" second.

- **3. Optional:** Edit dashboard(s).
 - 1) Click \checkmark to expand the added dashboard(s).
 - 2) Click 🔟 to edit the dashboard name or click 💼 to delete the dashboard.
- **4.** Add report(s) to a dashboard and edit the report(s).
 - 1) Select a report type and generate the report.
 - 2) Click **Add** on the report page to add the report to dashboard.
 - The report appears on the selected dashboard.
 - 3) Perform the following operations.
 - Add More Reports: Click Add Report to add more reports to the dashboard.
 - View Report in Larger Window: Click 🖃 to view the report in larger window.
 - Edit Report Name: Click --- and then click Edit.
 - Delete Report from Dashboard: Click --- and then click **Delete**.




Figure 26-1 Report Dashboard

- 5. Switch time to view report data.
 - 1) Select a dashboard and then click Switch Time to View to set the report type and time.

Report Type

Select the time basis for the reports. For example, daily report shows data on a daily basis.

Time

Set the specific time for generating the reports. For example, if you select **Custom Time Interval** as the report type, you can click is to specify a time interval for generating report data.

- 2) Click **Save** to change the default time basis of all the reports in the dashboard to the time you set in the previous sub step.
- 6. Optional: Export report(s) on the dashboard to the local PC.

IINote

See *Set General Parameters* for details about setting the saving path for the selected report(s).

- 1) Click **Export** to display the Export panel.
- 2) Select report(s) from the report list.
- 3) Select Excel, CSV, or PDF as the format of the exported report(s).
- 4) Click Export.

26.2 Generate People Counting Report

You can manually generate an entry & exit counting report to view the entry & exit statistics in a line chart or histogram. You can also export the report to the local PC.

Before You Start

Make sure you have properly configured the camera with a people counting rule for the required area. To configure the people counting rule, refer to the user manual of people counting camera.

Steps

- In the top left corner of the Client, select → All Modules → Intelligent Analysis → People Analysis → People Counting .
- 2. Select the analysis type.

People Counting for One Camera

A people counting report based on the data from the cameras you select will be generated. You can compare the data of different cameras.

People Counting in One Region

A people counting report based on the data from the people counting groups you select will be generated. You can compare the data of different groups.

iNote

Make sure you have added people counting groups. For details, refer to the User Manual of HikCentral Professional Web Client.

- **3.** Select people counting camera(s) or people counting group(s) based on the analysis type you set in the previous step.
 - Select Camera(s):
 - a. Click 📑 .
 - b. Select a current site or Remote Site from the drop-down list to show its people counting cameras.

IINote

- Only people counting cameras and people counting groups will be displayed here.
- Only the online cameras on the Remote Site will be displayed.
- c. Check the people counting camera(s) for statistics and click any position outside the selection region to go back to the Camera list.
- d. Check the cameras in the Camera list.

iNote

Up to 20 people counting cameras can be selected for statistics at the same time.

- Select Group(s):

Check the added people counting group(s) for statistics.

4. Set the report type to daily report, weekly report, monthly report, annual report, or customize the time interval for a report.

Daily Report

The daily report shows data on a daily basis. The system will calculate the number of people in each hour of one day.

Weekly Report, Monthly Report, Annual Report

As compared to daily report, weekly report, monthly report, and annual report can be less time-consuming, since they are not to be submitted every day. The system will calculate the number of people in each day of one week, in each day of one month, and in each month of one year.

Custom Time Interval

Users can customize the days in the report to analyze the number of people in each day or month of the custom time interval.

5. In the Time field, set the time or time period for statistics.

INote

For custom time interval report, you need to set the start time and end time to specify the time period.

6. Click Generate Report.




Figure 26-2 People Counting Report (Entry & Exit)

The statistics of all the selected item(s) are displayed in the right panel.

7. Optional: Perform the following operation(s) after generating the people counting report.

Show/Hide Certain Data	Click the legend to show or hide the data of a certain element, such as a certain camera.
View Entered/Exited/ Both Entered and Exited Statistics	Select Enter , Exit , or Enter and Exit from the drop-down list. The total statistics and all the selected cameras' statistics are displayed and marked with different colors.

View Both Entered and Exited Statistics of a Camera or Group	Click the camera or group name on the page below to view the chart of a camera or group.
View Linked Video	For line chart, if the selected report type is daily report, weekly report, or monthly report, click the line on the line chart to play the linked video.
	For histogram, if the selected report type is daily report, click the rectangle on the histogram to play the linked video.
Switch Between Line Chart and Histogram	Select 🗠 or 🝙 on the upper-left corner to switch between line chart (displaying the trend for the number of people on different time points) and histogram (for comparison).

8. Optional: Export the report to the local PC.

INote

See *Set General Parameters* for details about setting the saving path for the selected report(s).

1) Click Export.

The Export panel will display camera selected and time configured according to the range you defined previously.

- 2) (Optional) Select the camera or group and set the report type and report time if needed.
- 3) Select shorter time period to view more detailed data of each camera.

Example

For example, if you select Daily Report, you can select **By Day** or **By Hour**, and it will export 1or 24 records respectively for each camera.

IINote

If you select **By Minute**, the records amount depends on the configuration on the device. For example, if the device reports people counting data to the system every minute, it will export 24*60 records for each camera.

- 4) Set the format of the exported file as Excel, CSV, or PDF.
- 5) Click **Export** and the task will be displayed in the Download Center.

26.3 Generate People Density Analysis Report

You can manually generate a people density report to view the people density data in a line chart. You can also export the report to the local PC if required.

Before You Start

- Make sure you have purchased the License that supports people density analysis, or the function will be unavailable.
- Make sure you have added the behavior analysis server to the HikCentral Professional and linked cameras to the server. For details, see *HikCentral Professional Web Client User Manual*.
- Make sure you have configured people density analysis on the behavior analysis server. For details, see the user manual of the server.

Steps

- In the top left corner of the Client, select → All Modules → Intelligent Analysis → People Analysis .
- 2. Select camera(s) to search for people density data.
 - 1) Click 📭 to open the camera list.
 - 2) Optional: Check Include Sub-Area to allow the display of camera(s) in sub-areas.
 - 3) Select a current site or Remote Site from the drop-down site list.
 - 4) Select areas and then select the camera(s) in these areas.

IINote

- Only the online cameras will be displayed.
- You can also enter keywords of the camera name to search for cameras.
- 5) Check camera(s) appeared in the camera list for statistics.
- **3.** Set the report type to daily report, weekly report, monthly report, annual report, or customize the time interval for a report.

Daily Report

Daily report shows data on a daily basis. The system will calculate the peak amount of people appeared in the images of the camera in each hour of one day.

Weekly Report, Monthly Report, Annual Report

Compared to generating daily report, generating weekly report, monthly report, and annual report can be less time-consuming. The system will calculate the peak amount of people in each day of one week, in each day of one month, and in each month of one year respectively.

Custom Time Interval

Users can customize the days in the report to analyze the peak amount of people in each day or month of the custom time interval.

4. Select a pre-defined time period or customize a time period for search.

5. Click Generate Report.

People Density Analysis			+ Able to Databased (2) Second
Canasa		(c) Tarray R. (Mill 1997). In Convert, 2010, 2017. W Lease R. 2010, 2017. Insulate of Parallel	- terreli, Million, - Heresh, Mill, C. M. S.
lastic .		THE TAXABLE IN TAXABLE INTENTIN TAXABLE IN TAXABLE	
- 0 @ roken hanned 13 2 @ Some D. 2000 (10.000) 0 @ Some D. 2000 (20.000) 0 @ Some D. 2000 (20.000) 0 @ Some D. 2000 (20.000)			٨
# Grant Later, 20, 2010			1
 W General L, ACMU, HL, JULIU W Galera M, Statist HL, MILL, MILL 			
E General L 1980			1
2 Common Pay Statistical Statistics (Statistics)			
· Brannett, Milli (Musicity			
Convertigence (California)	15		
Carnes \$1,000100,01.00			
Convertigit-2000A02-23,1128,ee2/fr-ee	10 I		
Constant (1981) (ML) (1991)		*	
 Converticities in the Association of t			
The Content of Content			
· SPANNEL MILLER			
0	-	-	- X X
Report Tape			
Early Report	. 4		The second
Tem		*	Part of the second seco
rede-lar	+	sin his set out has not his and his yes his his his his his	a nod iron line most non non jone iron time bee-
	_	Dent. " Genet. " Genet. " Genet. " Dent. " Gene	
Constant Report :		[20] J. State K. R. J. Manus, M. J. Street B. M. Street B. R. J. Street B. R. Street B. Str	4,70.][meet,01.][tmark,0.][meet,8,]][test,8,]][test,8.]]

Figure 26-3 People Density Analysis Report

The statistics of all the selected camera(s) will be displayed on a line chart. **6. Optional:** Perform the following operations if required.

Add Report to Dashboard	 a. Click Add to Dashboard in the upper-right corner of the page. b. Create a report name. c. Select a dashboard. Or click New to create a new board and then select it. d. Click OK or Add and Go to Dashboard.
Show/Hide Certain Data	Click the legend to show or hide the data of certain element, such as certain camera.
View Statistics of a Camera	Select a camera at the bottom of the line chart to view its statistics in the line chart.
View Detailed Data in Each Time Segment	Hover the cursor onto the line chart to view the detailed data. For a daily report, you can view the peak amount of people appeared in the images of each camera in each hour; For a weekly report, in each day; For a monthly report, in each day; For a monthly report, in each month.
View Linked Video	Click the dot on the line chart to view the video of the time period that the dot represents.
	I IINote Viewing linked videos is not supported by annual report.

View Detailed Data in Each Minute

iNote

Viewing detailed data in each minute is only supported by daily report.

- a. Generate a daily report.
- b. Select a camera at the bottom of the line chart to display its statistics only.
- c. Hover the cursor onto the line chart and then click **Details** on the popup floating window.
 - The line chart that shows statistics in each minute will be displayed.
- d. Hover the cursor onto the newly-displayed line chart to view the peak amount of people appeared in the images of the camera in each minute.



Figure 26-4 View Detailed Data In Each Minute

7. Optional: Export the report(s) on the dashboard to the local PC.

Note

See *Set General Parameters* for details about setting the saving path for the selected report(s).

1) Click Export.

The Export panel will display the camera selected and time configured according to the range you defined previously.

- 2) **Optional:** (Optional) Select the camera and set the report type and report time if needed.
- 3) Select a shorter time period to view more detailed data of each camera.

Example

For example, if you select the daily report, you can select **By Day** or **By Hour**, and it will export 1or 24 records respectively for each camera.

IINote

If you select **By Minute**, the number of records depends on the configuration on the device. For example, if the device reports the data to the platform every minute, it will export 24*60 records for each camera.

- 4) Set the format of the exported file as Excel, CSV, or PDF.
- 5) Click Export and the task will be displayed in the Download Center.

26.4 Generate Queue Analysis Report

For cameras which support queue management, you can generate a report to show the number of queue exceptions and number of persons in each queue, and show the queue status including waiting duration and queue length.

Before You Start

Add a camera which supports queue management to the system and configure queue regions. To configure the queue region, refer to user manual of the camera.

Steps

- In the top left corner of the Client, select → All Modules → Intelligent Analysis → People Analysis → Queue Analysis .
- 2. Select camera(s) for statistics.
 - 1) Click 📭 in the camera panel.
 - 2) Select a current site or Remote Site from the drop-down site list to show its cameras.

i Note

Only the online cameras which support queue management will be displayed here.

3) Check the camera(s) for statistics.

The cameras will be added to the camera list.

3. Select the queue regions configured on the camera and the platform will collect the queue data in these queue regions.

Note

For configuring the queue, refer to the user manual of the camera.

4. Select the report type as daily report, weekly report, monthly report, or annual report.

Daily Report

Daily report shows data on a daily basis. The system will calculate the queue data detected in each hour of one day.

Weekly Report, Monthly Report, Annual Report

As compared to daily report, weekly report, monthly report, and annual report can be less time-consuming, since they are not to be submitted every day. The system will calculate the queue data detected in each day of way week, in each day of one month, and in each month of one year.

- 5. Set the time or time period for statistics.
- **6.** Select the analysis type and set the report range for daily report, weekly report, or monthly report.

Queuing-Up Time Analysis

The report will show the persons' queuing-up durations in different queues.

For example, if you set the report range to 300s and 600s, the report will show that in each queue, how many persons have waited for less than 300s, how many persons have waited for 300 to 600s, and how many persons have waited for more than 600s.

Queue Status Analysis

The report will show the number of queuing-up persons within different queuing-up durations.

For example, if you set the report range as 5 persons and 10 persons, the report will show that in each queue, how many seconds the status lasts when there are less then 5 persons, how many seconds the status lasts when there are 5 to 10 persons, and how many seconds the status lasts when there are more than 10 persons.

7. Click Generate Report.




Figure 26-5 Queue Analysis Report

A chart is displayed in the right panel, showing the number of exceptions (waiting timeout or people amount exceeding) of different queues.

8. Optional: Perform the following operation(s) after generating the report.

Show/Hide Certain Data	Click the legend to show or hide the data of certain element, such as queue.
View Queue Analysis Report of a Queue	Click the queue icon on the page below to view the report of a queue, including the number of exceptions, number of people in the queue, and waiting durations .
Switch Between Number of	Click 🔝 on the page below to view the report of all the selected queues.
Exceptions, Number of People, and Queue Length	If you select the report type as Daily Report , Weekly Report , or Monthly Report , and set the analysis type as Queue Status Analysis , click the drop-down list to view the number of waiting timeout exceptions, or number of people in different and all queues.
	If you select the report type as Annual Report , and set the analysis type as Queue Status Analysis , click the drop-down list to view the number of waiting timeout exceptions or number of people in all queues.
	If you select the report type as Daily Report , Weekly Report , or Monthly Report and set the analysis type as Queuing-Up Time Analysis , click the drop-down list to view the number of people amount exceeding exceptions or queue length of different queues.

If you select the report type as **Annual Report**, and set the analysis type as **Queuing-Up Time Analysis**, the people amount exceeding exceptions will show.

9. Optional: Export the report to the local PC.

Note

See *Set General Parameters* for details about setting the saving path for the selected report(s).

1) Click Export.

The Export panel will display with camera and queue selected and time configured according to the range you defined previously.

- 2) **Optional:** (Optional) Select the camera and queue, and set the report type and report time if needed.
- 3) Select shorter time period to view more detailed data of each queue.

Example

For example, if you select Daily Report, you can select **By Day** or **By Hour** and it will export 1 or 24 records respectively for each queue.

4) Select the content to export.

Queue Exception

The number of exceptions (people amount exceeding and waiting timeout) of each queue.

People Amount Exceeding

The number of persons in the queue exceeds the configured threshold.

Waiting Timeout

The waiting duration for the persons in the queue exceeds the configured threshold.

Person Amount in Queue

The number of persons in each queue.

Queue Status

The status of each queue, including persons' waiting duration and number of persons (queue length) in the queue.

5) For daily report, weekly report or monthly report, select analysis type.

6) Set the format of the exported file as Excel, CSV, or PDF.

7) Click Export and the task will be displayed in the Download Center.

26.5 Generate Heat Analysis Report

You can generate a heat analysis report to track consumer movements and analyze the visit times and dwell time in a configured area.

Before You Start

- Add a heat map network camera to the platform and properly configure the camera with heat map rule for the required area. To add a heat map network camera, please refer to the *User Manual of HikCentral Professional Web Client*. To configure the heat map rule, please refer to the user manual of heat map network camera.
- Add the camera to a static map. For details about how to add a camera to the static map, refer to *User Manual of HikCentral Professional Web Client*.

Steps

- In the top left corner of the Client, select All Modules → Intelligent Analysis → People Analysis → Heat Analysis .
- 2. Select analysis type.

Heat Analysis for One Camera

A heat analysis report based on the data from the selected cameras will be generated. The data of different cameras will be displayed and you can compare the data of different cameras.

Heat Analysis in One Region

A heat analysis report based on the data from the selected heat analysis groups will be generated. The data of different groups will be displayed and you can compare the data from different groups.

INote

You should have added heat analysis group(s). For details, refer to the User Manual of HikCentral Professional Control Client.

3. Select heat analysis camera(s) or heat analysis group(s) for statistics.

1) Click [1

IINote

- Only the online heat analysis camera(s) or heat analysis group will be displayed here.
- Up to 20 heat analysis cameras can be selected for statistics at the same time.

2) Check the heat analysis camera(s) or heat analysis group(s) for statistics.

4. Set the report type to daily report, weekly report, monthly report, annual report, or customize the time interval for a report.

Daily Report

Daily report shows data on a daily basis. The platform will calculate the number of people or people dwell time in each hour of one day.

Weekly Report, Monthly Report, Annual Report

As compared to daily report, weekly report, monthly report, and annual report can be less time-consuming, since they are not to be submitted every day. The platform will calculate the number of people or people dwell time in each day of way week, in each day of one month, and in each month of one year.

Custom Time Interval

Users can customize the days in the report to analyze the number of people or people dwell time in each day or month of the custom time interval.

5. Optional: Set the time or time period in the Time field for statistics.

INote

For custom time interval report, you need to set the start time and end time to specify the time period.

6. Set the analysis type.

Dwell Time

The minutes that the people stay at the same location during each time period for each camera.

People Amount

The number of people detected during each time period for each camera.



This analysis type is only supported by the second generation of heat analysis cameras.

Average Dwell Time

The average dwell time for the each person stay at the same location during each time period for each camera.

7. Click Generate Report.



Figure 26-6 Static Map of Selected Cameras

The static maps of the selected cameras will appear.

8. Click the map to view the detailed heat data of the cameras on the map. You can view each camera's field of view, and the fields are color coded. The red color block (255, 0, 0) indicates the most welcome region (most persons detected or longest dwell time), and blue color block (0, 0, 255) indicates the less-popular region (least persons detected or shortest dwell time).

IINote

Move the cursor to the field of view to view the detected value, including people amount or dwell time.

9. Optional: Click the camera icon on the page below to view heat analysis of a camera.




Figure 26-7 Heat Map of a Camera

The image of the camera is color coded. The red color block (255, 0, 0) indicates the most welcome region (most persons detected or longest dwell time), and blue color block (0, 0, 255) indicates the less-popular region (least persons detected or shortest dwell time).

You can drag the slider on the upper-right to adjust the range of the heat value. The heat data out of the range will not be displayed.

10. Optional: Click **E** is switch among heat map, histogram, line chart to view the details.



Figure 26-8 Line Chart of Heat Analysis

11. Optional: Export the report to the local PC.

INote

See *Set General Parameters* for details about setting the saving path for the selected report(s).

1) Click Export.

The Export panel will display with camera selected and time configured according to the range you defined previously.

- 2) (Optional) Select the camera, and set the analysis type and report time if needed.
- 3) Select shorter time period to view more detailed data of each camera.

Example

For example, if you select Daily Report, you can select **By Day** or **By Hour**, and it will export 1, 24 records respectively for each camera.

- 4) Set the format of the exported file as Excel, CSV, or PDF.
- 5) Click **Export** and the task will be displayed in the Download Center.

26.6 Generate Pathway Analysis Report

Pathway analysis is mainly used to analyze the people counting on the pathways in the shopping malls. With the help of fisheye cameras, the platform can collect the consumers data (for example, where the customers walk mostly) and translate that data onto a dashboard for mall managers. This helps managers analyze which areas/shops of the mall best catch a shopper's attention and which are overlooked. After setting the fisheye camera's pathways and their directions, the platform calculates the people dwell time at each pathway and number of people walking by, thus helps them make decisions.

Before You Start

- Properly add the camera to a static map and set its pathways on the map via the Web Client first. For details about adding camera to map and set pathways, refer to the User Manual of HikCentral Professional Web Client.
- You should have added pathway analysis groups. For details, see the user manual of the Web Client.

Steps

iNote

This function is only supported by the second generation of fisheye cameras.

- 1. In the top left corner of the Client, select
 → All Modules → Intelligent Analysis → People Analysis → Pathway Analysis .
- **2.** Select path analysis group(s) for statistics.
- **3.** Select the report type as daily report, weekly report, monthly report, annual report, or customize the time interval for a report.

Daily Report

Daily report shows data on a daily basis. The platform will calculate the number of people or people dwell time in each hour of one day.

Weekly Report, Monthly Report, Annual Report

As compared to daily report, weekly report, monthly report, and annual report can be less time-consuming, since they are not to be submitted every day. The platform will calculate the number of people or people dwell time in each day of way week, in each day of one month, and in each month of one year.

Custom Time Interval

Users can customize the days in the report to analyze the number of people or people dwell time in each day or month of the custom time interval.

4. Optional: Set the time or time period in the Time field for statistics.

IINote

For custom time interval report, you need to set the start time and end time to specify the time period.

5. Click Generate Report.




Figure 26-9 Pathway Analysis Report

The static map with the cameras and pathways color coded on the map will be displayed. The red color block (255, 0, 0) indicates the most welcome pathway (most persons detected or longest dwell time), and blue color block (0, 0, 255) indicates the less-popular pathway (least persons detected or shortest dwell time).

6. Move the cursor to the camera hot spot to view the line chart or heat map of the people amount and people dwell time in the pathways during this time period.



Figure 26-10 View Heat Map or Line Chart

7. Optional: Export the report to the local PC.

Note

See *Set General Parameters* for details about setting the saving path for the selected report(s).

1) Click Export.

The Export panel will display with camera selected and time configured according to the range you defined previously.

- 2) (Optional) Select the pathway analysis group and set the report type and report time if needed.
- 3) Select shorter time period to view more detailed data of each camera.

Example

For example, if you select Daily Report, you can select **By Day** or **By Hour**, and it will export 1, 24 records respectively for each camera.

- 4) Set the format of the exported file as Excel, CSV, or PDF.
- 5) Click Export and the task will be displayed in the Download Center.

26.7 Generate Person Feature Analysis Report

The platform supports saving features (including age and gender) of recognized human faces and generating reports in various time periods. The reports tells the percentage and number of people of different gender and age groups in different time period. It can be used in places such as shopping mall to analyze interests of people in different gender and age.

Before You Start

Make sure you have added a person feature analysis group if you want to perform feature analysis in one region. See *User Manual of HikCentral Professional Web Client* for details about adding a person feature analysis group.

Steps

- In the top left corner of the Client, select → All Modules → Intelligent Analysis → People Analysis → Person Feature Analysis .
- Select analysis type.

Feature Analysis for One Camera

Compare percentage and number of people of different gender and age groups detected by specified camera(s).

Feature Analysis in One Region

Compare percentage and number of people of different gender and age groups detected by the cameras in specified person feature analysis group(s) of multiple regions.

3. Select camera(s)/person feature analysis group(s).

IINote

- Only online cameras will be displayed.
- Up to 20 cameras/groups can be selected for statistics at the same time.
- The platform supports selecting one group of a Remote Site.
- **4.** Select the report type as daily report, weekly report, monthly report, annual report, or customize the time interval for a report, and the platform will generate statistics of the selected camera(s)/group(s) of the current day/week/month/year or the customized period.
- 5. Set the time or time period in the Time field for statistics.

IINote

For custom time interval report, you need to set the start time and end time to specify the time period.

6. Click Generate Report.




Figure 26-11 Person Feature Analysis

The statistics of all the selected cameras/groups are displayed on the right panel.

- 7. Optional: Click Add to Dashboard to display the report on the Dashboard.
- **8. Optional:** Export the report to the local PC.

IINote

See *Set General Parameters* for details about setting the saving path for the selected report(s).

1) Click Export.

The Export panel will display with camera selected and time configured according to the range you defined previously.

- 2) (Optional) Select the camera or group and set the report type and report time if needed.
- 3) Select shorter time period to view more detailed data of each camera.

Example

For example, if you select Daily Report, you can select **By Day** or **By Hour**, and it will export 1or 24 records respectively for each camera.

- 4) Set the format of the exported file as Excel, CSV, or PDF.
- 5) Click Export and the task will be displayed in the Download Center.

26.8 Generate Temperature Analysis Report

For thermal cameras, you can generate a report to show the number of exceptions (temperature too high or too low) and maximum/minimum temperature of different thermometry points on different presets.

Steps

- In the top left corner of the Client, select → All Modules → Intelligent Analysis → Temperature Analysis .
- 2. Select thermal camera(s) for statistics.
 - 1) Click 📑 in the camera panel.
 - 2) Select a current site or Remote Site from the drop-down site list to show its thermal cameras.

INote

Only the online thermal cameras will be displayed here.

3) Check the thermal camera(s) for statistics.

The cameras will be added to the camera list.

3. Select the preset(s) configured on the camera and the platform will collect the data on the thermometry point in these presets.

IINote

For configuring the thermometry point with temperature measurement rules, refer to the user manual of the thermal camera.

4. Select the report type as daily report, weekly report, monthly report, annual report, or customize the time interval for a report.

Daily Report

Daily report shows data on a daily basis. The platform will calculate the temperature data detected in each hour of one day.

Weekly Report, Monthly Report, Annual Report

As compared to daily report, weekly report, monthly report, and annual report can be less time-consuming, since they are not to be submitted every day. The platform will calculate the temperature data detected in each day of way week, in each day of one month, and in each month of one year.

Custom Time Interval

Users can customize the days in the report to analyze temperature data detected in each day or month of the custom time interval.

5. Set the time or time period in the Time field for statistics.

IINote

For custom time interval report, you need to set the start time and end time to specify the time period.

6. Click Generate Report.



Figure 26-12 Temperature Analysis Report

The temperature statistics of all the selected presets are displayed in the right panel. **7. Optional:** Perform the following operation(s) after generating the temperature report.

Show/Hide Certain Data	Click the legend to show or hide the data of certain element, such as certain preset or thermometry point.
View Temperature Report of Single Preset	Click the preset icon on the page below to view the report in the single preset.
View Temperature Report of Single Thermometry Point	 a. Click the preset icon on the page below to view the report in the single preset. b. In the Item for Comparison field, select one thermometry point. c. In the Item for Comparison field, select the indicator you want to view in the chart.

High/Low Temperature

Shows the number of exceptions that the temperature at this thermometry point is higher or lower than the pre-defined temperature.

Max. Temperature

Shows the maximum temperature at this thermometry point during the set time period.

The temperature is displayed in line chart, indicating the trend.

Min. Temperature

Shows the minimum temperature at this thermometry point during the set time period.

The temperature is displayed in line chart, indicating the trend.

8. Optional: Export the report to the local PC.

IINote

See *Set General Parameters* for details about setting the saving path for the selected report(s).

1) Click Export.

The Export panel will display with camera selected and time configured according to the range you defined previously.

- 2) (Optional) Select the camera and preset, and set the report type and report time if needed.
- 3) Select shorter time period to view more detailed data of each camera.

Example

For example, if you select Daily Report, you can select **By Day** or **By Hour**, or **By Minute** and it will export 1, 24, or 24×60 records respectively for each thermometry point.

4) Select the content to export.

Temperature Exception

Export the number of exceptions on temperature (temperature too high or too low) of each thermometry point.

Temperature Status

Export the maximum temperature and minimum temperature of each thermometry point. 5) Set the format of the exported file as Excel, CSV, or PDF.

6) Click **Export** and the task will be displayed in the Download Center.

26.9 Generate Vehicle Analysis Report

For ANPR cameras and entrances & exits, you can generate a report to show the number of passing vehicles detected by specified cameras during specified time periods.

Steps

- In the top left corner of the Client, select → All Modules → Intelligent Analysis → Vehicle Analysis .
- 2. Select ANPR or Entrance & Exit for the statistical type.
- **3.** Select ANPR camera(s) or entrance(s) & exit(s) for analysis.
- Select ANPR Camera:
 - a. Click 📑 in the camera panel.
 - b. Select a current site or Remote Site from the drop-down list to show its ANPR cameras which support this function.

iNote

Only the online ANPR cameras will be displayed here.

c. Check the camera(s) for analysis.

d. Select the camera(s) for the report in the camera list.

IINote

Up to 20 ANPR cameras can be selected for statistics at the same time.

- Select Entrance & Exit:

Check the entrance(s) & exit(s) for analysis.

4. Select the report type as daily report, weekly report, monthly report, annual report, or customize the time interval for a report.

Daily Report

The daily report shows data on a daily basis. The platform will calculate the number of vehicles in each hour of one day.

Weekly Report, Monthly Report, Annual Report

As compared to the daily report, the weekly report, monthly report, and annual report can be less time-consuming, since they are not to be submitted every day. The platform will calculate the number of vehicles in each day of way week, in each day of one month, and in each month of one year.

Custom Time Interval

Users can customize the days in the report to analyze the number of vehicles in each day or month of the custom time interval.

5. Set the time or time period for statistics.

IINote

For the custom time interval report, you need to set the start time and end time to specify the time period.

6. Click Generate Report.




Figure 26-13 Vehicle Analysis Report

The passing vehicles statistics detected by all the selected cameras are displayed in the right panel.

7. Optional: Export the report to the local PC.

IINote

See *Set General Parameters* for details about setting the saving path for the selected report(s).

1) Click Export.

The Export panel will display camera selected and time configured according to the range you defined previously.

- 2) **Optional:** Select the camera and set the report type and report time if needed.
- 3) Select a shorter time period to view more detailed data of each camera.

Example

For example, if you select the daily report, you can select **By Day** or **By Hour**, and it will export 1or 24 records respectively for each camera.

INote

If you select **By Minute**, the number of records depends on the configuration on the device. For example, if the device reports vehicle analysis data to the platform every minute, it will export 24*60 records for each camera.

- 4) Set the format of the exported file as Excel, CSV, or PDF.
- 5) Click **Export** and the task will be displayed in the Download Center.

26.10 Generate Skin-Surface Temperature Analysis Report

You can generate the skin-surface temperature analysis report to view the variation trend of the number of people with abnormal skin-surface temperature.

Before You Start

- Make sure you have added devices that support temperature screening to HikCentral Professional.
- Make sure you have enabled temperature screening on the device. For details, see the user manual of the device.

Steps

- 1. In the top left corner of the Client, select → All Modules → Intelligent Analysis → People Analysis → Skin-Surface Temperature .
- 2. Select the analysis type.

Temperature Screening Point

A skin-surface temperature report based on data from temperature screening points (e.g. cameras and visitor terminals) you select will be generated.

Person Group

A skin-surface temperature report based on the data from the person groups you select will be generated.

- 3. Select temperature screening point(s) or person group(s) for analysis.
 - Select Temperature Screening Point:
 - a. Click 📝 to open the camera list panel.

IINote

Only the online cameras will be displayed.

- b. (Optional) Check **Include Sub-Area** to select the sub-areas of the area that you have selected.
- c. Select an area in the area list to show the related temperature screening points.
- d. Check the temperature screening point(s) for screening.
- e. Select temperature screening point(s) for the report in the temperature screening point list.
- Select Person Group:

Check the person group(s) for screening.

INote

You can check **Select Sub-Groups** to select the sub-groups of the person group that you have selected.

4. Set the report type to daily report, weekly report, monthly report, or customize the time interval for a report.

Daily Report

The daily report shows data on a daily basis. The platform will calculate the peak amount of people appeared in the images of the camera in each hour of one day.

Weekly Report, Monthly Report

Compared to generating the daily report, generating the weekly report and monthly report can be less time-consuming. The platform will calculate the peak amount of people on each day of one week and on each day of one month respectively.

Custom Time Interval

Users can customize the days in the report to analyze the peak amount of people in each day or month of the custom time interval.

5. In the Time field, select a predefined time period or customize a time period for search.

6. Click Generate Report.




Figure 26-14 Skin-Surface Temperature Analysis Report

The statistics of the selected item(s) will be displayed.

7. Optional: Perform the following operations if required.

Show/Hide CertainClick the legend to show or hide the data of certain element, such
as certain camera.

View AbnormalIn the top left corner of the chart, select Abnormal Temperature orTemperature or NoNo Mask from the drop-down list to display the statistics of peopleMask Statisticswith abnormal temperature and without wearing face mask,
respectively.

Daily report only supports histogram.
Daily report only supports histogram
a. Click Add to Dashboard in the upper-right corner of the page.
b. Create a report name.
c. Select a dashboard. Or click New to create a new board and then select it.
d. Click OK or Add and Go to Dashboard.
to the local PC.

INote

See *Set General Parameters* for details about setting the saving path for the selected report(s).

1) Click Export.

- 2) **Optional:** Select the temperature screening point(s) or person group(s) and set the report type and report time if needed.
- 3) Select shorter time period to view more detailed data of each camera.

Example

For example, if you select Daily Report, you can select **By Day** or **By Hour**, and it will export 1or 24 records respectively for each camera.

- 4) Set the format of the exported file as Excel, CSV, or PDF.
- 5) Click Export and the task will be displayed in the Download Center.

Chapter 27 Maintenance

The Control Client allows you to monitor resource health status and search resource logs. The data of resource health status and resource logs, which is of especially importance for maintenance of the system, helps you locate the source of exceptions and determine methods for troubleshooting.

27.1 Health Monitoring

Health monitoring provides both near-real-time and history information about the status of the SYS and added resources. It is critical to multiple aspects of operating the servers or devices and is especially important for maintenance. When a resource exception occurs, you can enter this module to check the resource status and find out the abnormal device(s) and view the exception details.

27.1.1 Real-Time Health Status Overview

In the Health Monitoring module, you can view the real-time health status of the devices, servers, and resources managed on the platform. If there is no network transmission devices added, the Real-Time Overview page provides an at-a-glance view of the health status with charts and basic data of resource status.

In the top left corner of the client, select $\square \rightarrow$ All Modules \rightarrow Maintenance \rightarrow Health Monitoring and then click \blacksquare Real-Time Overview on the left.

Click **Real-Time Overview** tab at the top to enter the Real-Time Overview page.



Figure 27-1 Real-Time Health Status Overview

Section	Description
Resource Status	View the abnormal data of different resources (e.g., cameras, doors, elevators, or alarm inputs) added to areas of Central System in the graphical way. You can click the numbers and status types on the chart to view the real-time status details of resources or Remote Sites.
	Note
	The Remote Site status is only available for the Central System with Remote Site Management module (based on the License you purchased).
System Management Server Status	View the network health status and server running status. Click in the upper right corner of System Management Server panel to view the running status details of the server, including CPU usage, RAM usage, etc.

Section	Description
	Figure 27-2 System Management Server Status Details
Server Status	View the status (i.e., exception, warning, normal) of servers added on Central System. You can click the numbers and status types on the chart to view the real-time status details of servers.
Device Status	View the abnormal data of different devices (e.g., encoding devices, decoding devices, or access control devices) added on Central System. You can click the numbers on the chart to view the real-time status details of devices. If the icon appears at the top of device picture, it indicates that the device firmware should be upgraded. For upgrading the firmware, refer to <i>HikCentral Professional Web Client User Manual</i> .
Select Sites	Select one or multiple Sites (including Remote Sites) from the drop-down list in the upper left corner of Real-Time Overview page to display the status of resources on the selected Site(s).
Refresh	 Manually Refresh: Click Refresh in the upper right corner of Real-Time Overview page to manually refresh the resource status on the page. Auto Refresh: Management → System → Health Monitoring to set the interval for automatically refreshing the resource status on the page. See details in <u>Set Health Status</u> <u>Parameters</u>.

Section	Description	
Export Overview Page or Exception Data	Click Export in the upper right corner of Real-Tipage to export the page in PDF format. Or you Exception Data to export the exception data in format.	can check Export
	Export	×
	 By default, the exported file is in PDF format, and for PDF data sheet can be exported as EXCEL and CSV format. Export Exception Data 	exclusively. The
	Excel CSV Save	
Display on Smart Wall	Figure 27-3 Export Overview Page or Exce	
Display on Smart Wall	Click 📰 to display the overview page on the smart wall if you have added and configured smart walls on the platform .	

27.1.2 Real-Time Health Status Overview (Topology)

In the Health Monitoring module, you can view the real-time health status of the devices, servers, and resources managed on the platform. If there are network transmission devices managed on the platform, the Real-Time Overview page provides a topology of the managed devices. Topology is a figure that displays the connection relations among network transmission devices, surveillance devices, etc. It is mainly used for network maintenance.

IINote

- Make sure the network transmission devices have been added to the platform.
- If a network transmission device can not be recognized by the platform, it will be displayed as an unknown device.
- The topology does not support body cameras, but supports ticket dispensers.

In the top left corner of the client, click $\blacksquare \rightarrow$ All Modules \rightarrow Maintenance \rightarrow Health Monitoring $\rightarrow \blacksquare$ Real-Time Overview .

Click **Topology** tab at the top to enter the Topology page.



Figure 27-4 Topology Overview

Table 27-2 Topology Page

Section	Description	
Device Status	View the abnormal data of different devices (e.g., encoding devices, decoding device, or access control devices) added on the Central System. You can click the number to locate the abnormal device in the topology or view the devices' real-time status.	
	If the icon appears beside the device type name, it indicates that the device firmware should be upgraded. For upgrading the firmware, refer to <i>HikCentral Professional Web Client User</i> <i>Manual</i> .	
Resource Status	View the abnormal data of different resources (e.g., cameras, doors, elevators, or alarm inputs) added to the areas of the Central System. You can click the number to view the real-time status details of resources or Remote Sites.	

Section	Description	
	Note The Remote Site status is only available for the Central System with the Remote Site Management module (based on the License you purchased).	
Topology Details	View the relationships among devices, device information, link status, alarm information, etc. See details in <i>Topology Details</i> .	
Network Performance	View the current network performance (i.e., poor or good) of the System Management Server.	
System Management Server Status	View the network health status and server running status. Clickin the upper right corner of the System Management Server panel to view the running status details of the server, including its CPU usage, RAM usage, etc.if if i	
Server Status	View the status (i.e., exception, warning, normal) of servers added on the Central System.	
Generate Topology Again	Click Refresh → Generate Topology Again to draw the network topology again.	
Refresh	 Manual Refresh: Click Refresh in the upper right corner of the Real-Time Overview page to manually refresh the resource status on the page. Auto Refresh: Management → System → Health Monitoring to set the interval for automatically refreshing the resource 	

Section	Description	
	status on the page. See details in <u>Set Hea</u> <u>Parameters</u> .	<u>ılth Status</u>
Export Topology or Exception Data	 Click Export in the upper right corner of Topology page a select the export type as Default or Only Topology to extopology in PDF format or the exception data in Excel/CS format. If the export type is selected as Default, the whole disinformation (topology and exception data) on the Heat Monitoring page will be exported. If the export type is selected as Only Topology, only the topology will be exported in PDF format. 	
	Export Select thems to Export Default Default Default the exported file is in CDF tornat, and the file Default the exported file is in CDF tornat, and the file Default the exported file is in CDF tornat, and the file Default toreption Data Default	mat
Display on Smart Wall	Click store to display the overview page on the have added and configured smart walls on the store the store that the store th	

Topology Details

The topology of devices will display the hierarchical relationships among the devices, device information, link status, alarm information, etc.




Figure 27-7 Topology Details

Device Node

The device nodes are displayed by icons, including the System Management Server, Recording Server, network transmission device, encoding device, access control device, video intercom device, network bridge, fiber converter, etc. Each device node displays the device name and IP address.

INote

- When the device information (device name, IP address, online/offline status) changes, you should manually refresh to generate the topology again or set auto-refresh.
- When the device hierarchy or physical connection changes, you should manually refresh to generate the topology again.
- If the node icon is displayed in red, it indicates that the device is abnormal or alarms are triggered. You can view the reason for device exception or alarm details.
- For the added online devices, the displayed device alias is the same as the device IP address.

View Device Details

Click the device node in the topology and click **Details** in the drop-down list. You can view the device details, including the basic information (i.e., device name, IP address and device model), device usage (e.g., RAM usage, CPU usage, PoE power), arming status and disk array (for

encoding device), live video (if the device is linked with a camera), linked lane name / entrance direction / entrance & exit name / barrier control status (if the entrance and exit is linked with a camera), device panel status (i.e., ports and ports usage), and port information (i.e., port name, and peer device type, peer device IP address, and peer device name).

Switch01			C Reboot Switch
Device Status	Port Status	Port Statistics	Device Alarm
Basic Information			
	Device Name:	Switch01	
	IP Address:	192.368.32.40	
	Device Model:	05-361316-61	
Device Usage			
	Network Status:	Online	
	RAM Usage:	_	43%
	CPU Usage:	-	24%
	PoE Power:	-	0W/0W
PoE Power P	eak Value (Last 7 Days):		0W/0W
Device Panel Status			
RJ45 Port		Alar	m Normal Disconnect
HERVESION			
Port Information			

Figure 27-8 View Device Details

IINote

The device details vary with different device models.

Link

The color of link indicates the utilization rate of network bandwidth (red: congested, yellow: busy, gray: fluent). And the shape of link indicates the link type (wireless, network link, optical fiber).

View Link Details

Move the cursor to the link between nodes to display the link details. You can view the upstream rate and downstream rate to determine whether the network status is normal or not. You can also view the connected device type, IP address, port name, and port status.




Figure 27-9 View Link Details

View Connection Path

If there is a data transmission failure between the devices, you can view the connection path to judge which link is disconnected, so as to restore the link as quickly as possible. Click the device node and in the topology and click **Show Connection Path** in the drop-down list. According to the information presented in the prompt window, click **Common Unknown Node** or **Select Node** to

select the peer node, and then click **OK**. After that, the connection path between the two nodes will be displayed.

Remote Configuration

Click the device node in the topology and click **Remote Configuration** in the drop-down list to configure the device parameters, including system settings, network and port configuration. You can configure the network parameters and device port according to the network usage. For details, refer to the user manual of the device.

iNote

This function should be supported by the device.

View Device Logs

When a device failure happens or trouble shooting is required, you can view the device's logs to know the alarms, notifications, operations and events of the device. Click the device node in the topology and click **View Device Logs** in the drop-down list to enter the Device Logs page, and you can set the conditions to search the device logs.

iNote

This function should be supported by the device.

Set as Root Node

When you need to adjust the topology structure, you can click the device node in the topology and click **Set as Root Node** in the drop-down list to set the node as the root node.

IINote

Only the switch, wireless network bridge, and fiber converter can be set as root node.

Zoom In/Zoom Out

Click **+** or **-** to zoom in or zoom out the device node(s) and the subsidiary device node(s). You can scroll the mouse wheel to zoom in or zoom out the topology.

Adjust Topology

Click the background of the topology to move the topology in up, down, right, or left direction.

Full Screen

Click 📰 on the upper-right corner of the topology to display the topology in full-screen mode.

Adaptive View

Click on the upper-right corner of the topology to adapt the topology to the current window, to help you know the whole topology hierarchy quickly.

Search

By entering the device name or IP address in the search box, you can quickly locate the device on the topology.

27.1.3 Historical Health Data Overview

You can view the historical online rate of resources and devices, or the recording integrity rate.

In the top left corner of Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Maintenance \rightarrow Health Monitoring and then click \blacksquare History Status Overview on the left.

			at testinal III the
Annual Dates Los			
In a service and the service of the	and the second second	the little change in	Office laws of
	Planet II	areas)	
		1794	
	100		
	Constant of Consta		
	(inset if		
and a finite face			
	and the second second	field office families #	the loss 4
	The summer of		
	9		
	No.	1000	
vierdig inspire here			

Figure 27-10 Historical Health Data Overview

Section	Description
Filter Data	Select a time period from the drop-down list in the upper right corner of each section for filtering data by day, week, or month.
Resource Online Rate	 On the line chart, you can perform the following operations: Move the cursor on the line chart to view the camera online rate and the number of offline cameras at specific time points. Click the a dot on the line to go to Resource Log page to view the detailed network status of cameras at that time point. On the doughnut chart, you can perform the following operations:

Table 27-3 Historical Health Data Page

Section	Description
	 Move the cursor to red part of the doughnut chart to view the number of the cameras which once were offline and the offline rate during the time period you select. Move the cursor to the green part of the doughnut chart to view the number of the cameras which stay online and the online rate during the time period you select. On the table, you can do one of the followings: Click Total Offline Duration to rank the cameras in terms of total offline duration within the time period you select. Click Offline Times to rank the cameras in terms of offline times within the time period you select.
Device Online Rate	 On the line chart, you can do one of the followings. Move the cursor on the line chart to view the device online rate and the number of offline devices at specific time points. Click the a dot on the line to go to Device Log page to view the detailed network status of devices at that time point. On the doughnut chart, you can perform the following operations. Move the cursor to red part of the doughnut chart to view
	 the number of the devices which once were offline and the offline rate during the time period you select. Move the cursor to the green part of the doughnut chart to view the number of the devices which stay online and the online rate during the time period you select. On the table, you can do one of the followings. Click Total Offline Duration to rank the devices in terms of total offline duration within the time period you select. Click Offline Times to rank the devices in terms of offline times within the time period you select.
Recording Integrity Rate	On the line chart, you can move the cursor to view the recording integrity rate at specific time points. Click the a dot on the line to go to Device Log page to view the detailed resource status of devices at that time point.
Select Site	Select a Current or Remote Site from the drop-down list in the upper left corner of History Overview page to display the historical data of resources on the Site.

Section	Description	
Refresh	 Manually Refresh: Click Refresh in the upper right corner of History Overview page to manually refresh the data on the page. Auto Refresh: Management → System → Health Monitoring to set the interval for automatically refreshing the data on the page. See details in <u>Set Health Status Parameters</u>. 	
Export Overview Page or Exception Data	Click Export in the upper right corner of History Overview page to export the page in PDF format. Or you can check Export Exception Data to export the exception data in Excel/CSV format.	
	 By default, the exported file is in PDF format, and for PDF exclusively. The data sheet can be exported as EXCEL and CSV format. Export Exception Data Excel CSV Save Figure 27-11 Export Overview Page or Exception Data	

27.2 Resource Status

You can monitor the status of the added resources, such as cameras, encoding devices, Recording Servers, Streaming Servers, etc., which helps you find out and maintain the abnormal resources in time, ensuring the smooth running of the platform to the greatest extent.

On the top left corner of the client, select $\blacksquare \rightarrow$ All Modules \rightarrow Maintenance \rightarrow Resource Status , and select a resource type on the navigation panel on the left.

IINote

You can view the status of cameras, UVSSs, Streaming Servers, Recording Servers, encoding devices, dock stations, and decoding devices added on the Remote Sites via the Resource Status module of Central System.

Camera Status

On the camera status page, you can view camera status, such as network status, arming status, and recording status.

You can also perform the following operations.

- Select a Remote Site from the drop-down list in the camera list panel to display the status of cameras on the Remote Site.
- Click the camera name to view its status and basic information.
- Click the IP address to view the status of the device to which the camera is related.
- Click 😰 in the Operation column to go to the Web Client to configure the parameters of the specified camera.
- Click
 in the Operation column to view the online/offline records of the specified camera. For
 details, see <u>Search for Online/Offline Logs of Resource</u>.

IINote

This operation is not available for the cameras added on Remote Sites.

• Click 📹 in the Operation column to view the recording status of the camera. For details, see *Search for Recording Status of Resource*.

INote

This operation is not available for the cameras added on Remote Sites.

- Click View Camera with Abnormal Image to view the videos of cameras with abnormal images. And you can also export the image diagnosis results of selected camera(s) or all cameras in PDF format.
- Select the device type(s) from the first drop-down list on the top to filter the camera status by device type.
- Check the check box and select the exception type from the second drop-down list on the top to filter the camera status by exception type.

iNote

Contact the admin user to edit the abnormal configurations of camera's event or alarm via the Web Client if an icon () appears near the camera name.

Door Status

On the door status page, you can view the information such as the network status of related devices and door status.

IINote

For the door linked to the video intercom device, the door status is not available to be displayed.

You can also perform the following operations.

- Click the door name to view the status details and basic information.
- Click the device name to view the status of the device to which the door is related.

- Click I in the Operation column to go to the Web Client to configure the parameters of the specified door.
- Click
 in the Operation column and select a control type from the drop-down list to control the door status.
 - **Unlock**: When the door is locked, unlock the door and it will be open. After the open duration (configured via the Web Client), the door will be closed and locked again automatically.
 - **Lock**: When the door is unlocked, lock the door and it will be closed. The person who has the access permission can access the door with credentials.
 - **Remain Unlocked**: The door will be unlocked (no matter closed or open). All the persons can access the door with no credentials required (free access).

For the door linked to video intercom device, setting its status to remain unlocked is not available.

- **Remain Locked**: The door will be closed and locked. No person can access the door even if he/she has the authorized credentials, except the super users.
- Check the check box and select the exception type from the drop-down list on the top to filter the door status by exception type.

Elevator Status

On the elevator status page, you can view information, such as the network status of elevator control devices and the card reader status.

You can also perform the following operations.

- Click the name to view the status details and basic information.
- Click the device name to view the status of the device to which the elevator is related.
- Click 🗊 in the Operation column to go to the Web Client to configure the parameters of the specified elevator.
- Check the check box and select the exception type from the drop-down list on the top to filter the elevator status by exception type.

Alarm Input Status

You can view the alarm input status including resource usage status (online or offline), arming status, bypass status, fault status, alarm status, detector connection status, battery status, and so on.

You can also perform the following operations.

- Click the device name to view the status of the device to which the alarm input is related.
- Select the device type(s) from the first drop-down list on the top to filter the alarm input status by device type.
- Check the check box and select the exception type from the second drop-down list on the top to filter the alarm input status by exception type.

UVSS Status

On the UVSS status page, you can view the information such as line scan camera status and capture camera status.

You can also perform the following operations.

- Click the UVSS name to view the status details and basic information.
- Select a Remote Site from the drop-down list at the top of UVSS status page to display the status of UVSSs on the Remote Site.
- Click 🗊 in the Operation column to go to the Web Client to configure the parameters of the specified UVSS.

iNote

This operation is not available for the UVSSs added on Remote Sites.

• Check the check box and select the exception type from the drop-down list on the top to filter the UVSS status by exception type.

Remote Site Status

In the Remote Site status page, you can view the Remote Site status such as the network status and default stream (it refers to the default stream type for accessing the resources on the Remote Site).

You can also perform the following operations.

- - **Automatically Judge**: The system will automatically judge the condition of network connection and then set the device access mode accordingly as accessing directly or accessing via Streaming Gateway and Management Service.
 - **Proxy**: The system will access the device via Streaming Gateway and Management Service.
- Click **Restore All Network Connections** to restore the connection mode of all the added Remote Site's resources to **Automatically Judge** mode.
- Select the Remote Site(s) and click **Switch Stream** to switch the stream type. When starting live view of the Remote Site's resources in Central System, the Control Client will get this default stream to start live view.
 - **Main Stream:** Main stream provides higher quality video, higher resolution, but brings about higher bandwidth usage.
 - **Sub-Stream:** Sub stream can save on bandwidth, but the video quality is lower than main stream.
 - **Smooth Stream:** This stream type is usually used in low-bandwidth situation. After switching to smooth stream, the live view and playback will be smoother in slow network performance, but the image quality will be lower accordingly.
 - Default Stream Type: If you select Default Stream Type, the stream type for accessing the selected Remote Site's resources will be restored to the global stream type you set in System → Video → Network.

Streaming Server Status

You can view the streams via each added Streaming Server (including incoming streams and outgoing streams), and view the hardware status such as network status, CPU usage, and RAM usage.

You can also perform the following operations.

- Click the Streaming Server name to view the status details and basic information.
- Check the check box and select the exception type from the drop-down list on the top to filter the Streaming Server status by exception type.

Recording Server Status

You can view the status and information of Recording Server, such as the recording status, CPU usage, RAM usage, HDD status, and so on.

You can also perform the following operations.

- Click the Recording Server name to view the status details and basic information.
- Select a Remote Site from the drop-down list at the top to display the status of Recording Servers on the Remote Site.
- Click the status in Recording Status column to view the recording status of the channels configured to store the video files in this Recording Server.
- Click the status in Hardware Status or HDD Status column to view the hardware status and HDD exception details if the status is exceptional.
- Check the check box and select the exception type from the drop-down list on the top to filter the Recording Server status by exception type.

DeepinMind Server Status

You can view the network status, CPU usage, and RAM usage, etc., of the DeepinMind Servers, and click the server name to view the status details and basic information.

You can also check the check box and select the exception type from the drop-down list on the top to filter the DeepinMind Server status by exception type.

Security Audit Server Status

You can view the HDD status, network status, and first added time, etc., of the Security Audit Server, and click the server name to view the status details and basic information.

You can also check the check box and select the exception type from the drop-down list on the top to filter the Security Audit Server status by exception type.

Encoding Device Status

You can view the encoding device status including the recording status, HDD usage, arming status, default stream (it refers to the default stream type for accessing the resources of the encoding device), etc.

You can perform the following operations.

- Select a Remote Site from the drop-down list at the top to display the status of encoding devices on the Remote Site.
- Click the device name to view the status and basic information of the encoding device and the related cameras.
- Click the status in **Recording Status** column to view the recording status of channels configured to store the video files on this encoding device.
- Click 🗊 in the Operation column to go to the Web Client to configure the parameters of the specified encoding device.
- Click \square to wake up the encoding device if it is in sleep mode.
- Click in the Operation column to view the online/offline records of the encoding device. For details, see <u>Search for Online/Offline Logs of Device</u>.
- Click **Switch Device Access Mode** to switch the access mode for the Control Client to access the devices.
 - Restore Default: Restore the device access mode as configured in the System → Device Access Mode on the Web Client.
 - Automatically Judge: Judge the device access mode according to the current network.
 - **Directly Access**: Access the device directly, not via HikCentral Professional Streaming Service.

iNote

When the encoding device is in the same LAN with the SYS server, the Direct Access mode is not available.

- Proxy: Access the device via HikCentral Professional Streaming Gateway and HikCentral Professional Management Service. It is less effective and less efficient than accessing directly.
- Select the encoding device(s) and click **Switch Stream** to switch the stream type. When starting live view, the Control Client will get this default stream to start the live view of the encoding device's resources.
 - **Main Stream:** Main stream provides higher quality video, higher resolution, but brings about higher bandwidth usage.
 - **Sub-Stream:** Sub stream can save on bandwidth, but the video quality is lower than main stream.
 - **Smooth Stream:** This stream type is usually used in low-bandwidth situation. After switching to smooth stream, the live view and playback will be smoother in slow network performance, but the image quality will be lower accordingly.
 - Default Stream Type: If you select Default Stream Type, the stream type for accessing the selected encoding device(s) will be restored to the global stream type you set in System → Video → Network.
- Check the check box and select the exception type from the drop-down list on the top to filter the encoding device status by exception type.

Access Control Device Status

You can view the status and information such as network status and battery status of the added access control devices. If the device is turnstile, you can view the status of master lane controller, slave lane controller, and component.

You can perform the following operations.

- Click the device name to view the status and basic information of the access control device, and the related doors and cameras.
- Click 💿 in the Operation column to go to the Web Client to configure the parameters of the specified access control device.
- Check the check box and select the exception type from the drop-down list on the top to filter the Access Control Device status by exception type.

Elevator Control Device Status

You can view the information such as network status, arming status, and distributed elevator controller status.

- Click the device name to view the status and basic information of the elevator control device, and the related floors and cameras.
- Click 💿 in the Operation column to go to the Web Client to configure the parameters of the specified elevator control device.
- Check the check box and select the exception type from the drop-down list on the top to filter the elevator control device status by exception type.

Video Intercom Device Status

You can view the status information of the video intercom device such as network status, arming status, and the status of calling center from device (whether the device is able to call the surveillance center of the platform).

You can perform the following operations.

- Click **All Devices** and then select a device type to display the device status of selected type only.
- Click the device name to view the status and basic information of the video intercom device, and the related doors and cameras.
- Click 💿 in the Operation column to go to the Web Client to configure the parameters of the specified video intercom device.
- Select the device type(s) from the first drop-down list on the top to filter the video intercom device status by device type.
- Check the check box and select the exception type from the second drop-down list on the top to filter the video intercom device status by exception type.

Security Control Device Status

You can view the managed devices' network status, battery status, and so on. You can perform the following operations.

- Click All Devices and then select a device type to display the device status of selected type only.
- Check the check box and select the exception type from the drop-down list on the top to filter the security control device status by exception type.
- Click the device name to view the status and basic information of the security control device, and the related alarm inputs and cameras.
- Click 💿 in the Operation column to go to the Web Client to configure the parameters of the specified security control device.

Dock Station Status

You can view the network status, HDD status, file backup status, and so on, of the added dock station.

You can perform the following operations.

- Select a Remote Site from the drop-down list at the top to display the status of dock stations on the Remote Site.
- Click the device name to view the status and basic information of the dock station.
- Click I in the Operation column to go to the Web Client to configure the parameters of the specified dock station.
- Check the check box and select the exception type from the drop-down list on the top to filter the dock station status by exception type.

Network Transmission Device

You can view the network transmission devices' CPU usgae, RAM usage, PoE usage, occupied ports, and so on.

You can perform the following operations.

- Click All Devices and then select a device type to display the device status of selected type only.
- Check the check box and select the exception type from the drop-down list on the top to filter the network transmission device status by exception type.
- Click the device name to view the basic information, device usage, and port information of the network transmission device.
- Click 💿 in the Operation column to go to the Web Client to configure the parameters of the specified network transmission device.

Decoding Device Status

You can view the status information such network status, first added time, and checking time. You can perform the following operations.

- Select a Remote Site from the drop-down list at the top to display the status of decoding devices on the Remote Site.
- Click the device name to view the status and basic information of the decoding device.
- Click I in the Operation column to go to the Web Client to configure the parameters of the specified decoding device.

Security Inspection Device

You can view the security inspection devices' network status, IP address, serial No., and so on. You can perform the following operations.

- Click All Devices and then select a device type to display the device status of selected type only.
- Check the check box and select the exception type from the drop-down list on the top to filter the security inspection device status by exception type.
- Click the device name to view the status and basic information of the security inspection device.

- Click 😰 in the Operation column to go to the Web Client to configure the parameters of the specified security inspection device.
- Click in the Operation column to view the online/offline records of the security inspection device. For details, see <u>Search for Online/Offline Logs of Device</u>.

Common Operations

You can perform the following operations for different resource types.

- Check Include Sub-area to display the resources of child areas.
- Check the checkbox in the top right of status display page to select exception types from the drop-down list to filter the resource status.
- Click **Export** to export the status data as CSV or Excel to the local PC.
- Click 🗇 in the Operation column to refresh the status of the specified resource, or click **Refresh** to refresh the status of all resources displayed on the page.

IINote

The resource status will be automatically refreshed in a specified interval (see details in <u>Set</u> <u>Health Status Parameters</u>).

27.3 Log Search

Three types of log files are provided: server logs, device logs, and resource logs. The server logs refer to the logs files stored in the SYS server on the Current Site and the Remote Site; The device logs refer to the log files stored on the connected devices, such as encoding device and security control device; The resource logs refers the logs about camera recording status and online status. You can search the log files, view the log details and backup the log files.

27.3.1 Search for Server Logs

You can search for server logs of the current site or Remote Sites, which contain error logs, warning logs and information logs. Server logs contain historical user and server activities. You can search for the logs and then check the details.

Steps

1. In the top left corner, select $\blacksquare \rightarrow$ All Modules \rightarrow Maintenance \rightarrow System Log \rightarrow Server Logs.

Server Logs	
Site	
	~
Туре	
Search	
> Error	
> 🗌 Information	
> 🗆 Warning	
Source	
Search	
>	
>	
Resource Name	
Time	
*. d	0
Search	

Figure 27-12 Search for Server Logs

- 2. In Site, select the current site or a Remote Site.
- 3. In Type, select one or multiple log types and sub types.

IINote

Error logs record failures or errors. Warning logs record license expiration events. Information logs refer to other general logs which record successful or unknown operation results.

- **4.** In **Source**, select user and server to set the source of the logs that you want to search for.
- 5. Optional: In Resource Name, enter the name of a resource to search the logs of the resource.
- 6. In Time, select the time range of this search.

You can select **Custom Time Interval** to set a precise start time and end time.

7. Click Search.

All matched logs are listed with details on the right.

8. Optional: Check all or specific logs, click **Export**, and then select a file format (i.e., Excel or CSV) to download the searched logs as a single file to your local PC.

27.3.2 Search for Online/Offline Logs of Device

You can search for the online/offline logs of encoding devices, security inspection devices, and mobile devices. The online/offline logs provide information on the current device status (online or offline), latest offline time, total offline duration, etc.

Steps

1. In the top left corner, select $\blacksquare \rightarrow$ All Modules \rightarrow Maintenance \rightarrow System Log \rightarrow Device Logs .

Device Logs	
Typer	
Coles/Offening Using or dense	
Device	
Drooding Device	
See 8	
II AK	-
the stations	-
C - management and	
D Restinguisting	
C 🐜 Prinsenter	
C B NEW YORK	
12 Martin Constanting	
15 🗰 (part cost)	
D = faguages	
- M PARTING AND	
D 🗰 Address Management	
D - Control Transmission	
Security Security	
12 - 100	
12 🗰 Marina	
Se Manager	
ta 🐂 kantinaan.	
Time	
Land 24 Hours	~
Differ Caralitan	
C	
Search	



- 2. In Type, select Online/Offline Log as the log type.
- **3.** Select a device type and check the devices you want to search.
- 4. In Time, specify the time range of this search.

You can select **Custom Time Interval** to set a precise start time and end time.

- 5. Optional: If there are a large number of devices, check Filter Condition to set a range of total offline times during the specified time range to filter the devices, or set a total offline duration to filter the devices.
- 6. Click Search.

The offline/online log of each device are listed on the right. You can check the name, IP address, current status (online/offline), latest offline time, total offline times, and total offline duration of each device.

7. Optional: Perform further operations after searching for device logs.

View Offline	Click on device name to view history online duration (displayed as a line chart) and status (displayed as a list) of the device.
History	 You can perform the following operations. Filter Data: Select a time period and a status (online, offline or all) from the drop-down lists respectively to filter the data. View Details: Move the cursor to the line chart to view the detailed offline and online duration at each time point.
View Device Logs	Click 📖 in the Operation column to view the logs stored on the device.
Export Logs	Click Export and then select a file format (i.e., Excel or CSV) to download the searched logs as a single file to your local PC.

27.3.3 Search for Logs Stored on Device

You can search for the logs stored on encoding devices, security control devices, decoding device, access control devices, elevator control devices, and network transmission devices.

Steps

1. In the top left corner, select $\blacksquare \rightarrow$ All Modules \rightarrow Maintenance \rightarrow System Log \rightarrow Device Logs .

Online Office Ling	· Log on Device	
erica		
rooding Device		+
-		- 63
-		
90 - C - C - C - C - C - C - C - C - C -		
Set 1 manufacture		
Second.	C Martine Information	
17 Auto		
T boston		
D Opentor,		
T effendiet		
ille -		

Figure 27-14 Search for Logs Stored on Device

- 2. Select Log on Device as the log type.
- **3.** Select a device type and select the device you want to search.
- **4.** Select the main event as **Normal** or **Battery Information** and check the sub event(s) to be searched for.
- 5. Specify the time range of this search.

You can select **Custom Time Interval** to set a precise start time and end time.

6. Click Search.

All matched logs are listed with details on the right.

7. Optional: Click **Export** and then select a file format (i.e., Excel or CSV) to download the searched logs as a single file to your local PC.

27.3.4 Search for Online/Offline Logs of Resource

You can search for the online/offline logs of cameras on the current site. The online/offline logs provide information on the current device's status (online or offline), latest offline time, total offline duration, etc.

Steps

In the top left corner, select → All Modules → Maintenance → System Log → Resource Logs .

ype		
 Online/Offline Lo 	g i Recording Status	
amera		D
Search		
	No data.	
ime		
Last 7 Days		~
Filter Condition		

Figure 27-15 Search for Resource Online/Offline Logs

- 2. In Type, select Online/Offline Log.
- 3. Click 📑 to show the area list on the current site and then select the cameras whose logs are to be searched for.
- 4. Optional: Modify your selection in the selected camera list.

Remove a Camera Click in to remove the camera from the list.

Remove All Cameras Click in to remove all cameras in the list.

5. In **Time**, specify the time range of this search.

Note

You can select **Custom Time Interval** to set a precise start time and end time.

- 6. Optional: If there are a large number of resources, check Filter Condition to set a range of total offline times during the specified time range to filter the resources.
- 7. Click Search.

The offline/online log of each resource are listed on the right. You can view the name, IP address, current status (online/offline), latest offline time, total offline times, and total offline duration of each resource.

8. Optional: Perform further operations after searching fro resource logs.

View Offline History	Click resource name to view history online duration (displayed as a line chart) and status (displayed as a list) of the resource.		
	You can perform the following operations.		
	 Filter Data: Select a time period and a status (online, offline or all) from the drop-down lists respectively to filter data. View Details: Move the cursor to the line chart to view the detailed offline and online duration at each time point. 		
View Device Online/ Offline Logs	Click the IP address to view the online/offline logs of the device where the resource is linked.		
Export Logs	Click Export and then select a file format (i.e., Excel or CSV)to download the searched logs as a single file to your local PC.		

27.3.5 Search for Recording Status of Resource

You can search for the recording status of cameras on the current site. The recording status includes the recording integrity rate, total time length abnormal recording, times of recording interruptions, etc.

Steps

In the top left corner of the Client, select ⇒ All Modules → Maintenance → System Log → Resource Logs.




Figure 27-16 Search for Resource Recording Status

- 2. In Type, select Recording Status.
- 3. Click 📭 to show the area list of the current site and then select the cameras whose logs are to be searched for.
- 4. Optional: Modify your selection in the selected camera list.

Remove a Camera Click 📑 and then click 📋 to remove a camera from the list.

Remove All Cameras Click 📑 and then click 💼 to remove all cameras in the list.

5. In Time, specify the time range of this search.

Note

You can select **Custom Time Interval** to set a precise start time and end time.

6. Optional: If there are a large number of resources, check Filter Condition and set the filter conditions.

Retention Duration (Days)

Set a range of the retention duration of the recorded video footage to filter the cameras.

Recording Integrity Rate

Set a range of the recording integrity rate to filter cameras. The recording integrity rate refers to the percentage obtained from dividing the actual recording duration by the scheduled recording time.

IINote

For details about recording schedule, refer to the *HikCentral Professional Web Client User Manual*.

7. Click Search.

Recording status of each camera are listed on the right, including camera name, camera IP address, area where the camera belong, video storage type, etc.

Start Time

The time when the camera started recording.

End Time

The latest time when the camera was recording.

Retention Duration (Days)

The retention duration (unit: day) of the recorded video footage refers to the duration between **Start Time** and **End Time**.

Total Length

The total time length of video storage.

Abnormal Total Length

The total time length of the video loss within the scheduled time.

Recording Interruption

The total times of recording interruption within the scheduled time.

8. Optional: Check historical recording status.

1) **Optional:** Click **Rule** in the top right corner to view the analytical rules for history videos.

				Contraction States
ltorage Type			0	Supported O Not Supported
Storage Type		Real-Time Storage		Scheduled Copy-Back
Type	Scheduled Time	Event Recording	Command-based	ANR Video File
Start Time	0	۲	۲	•
End Time	٥	0	0	0
Number of Days	0	۲	0	•
Total Length	•	0	0	0
Abnormal Total Length	•	0	0	0
Recording Interruption	•	•	0	0
Recording Integrity Rate	٥	٢	0	0
Recording Details	0	0	0	0
Abnormal Recording De	0	٢	۲	0
	End Time Res Number of Days: End Total Length: Tot Abronnal Total Length: Tot Recording Interruption: Tot	al Recording Length		

Figure 27-17 Analytical Rules for History Video

2) Click a camera name to open the History Recording Status panel.



Figure 27-18 History Recording Status

The blue parts on the time bars represent the time periods during which video footage were recorded. The orange parts on the time bars represent the time periods during which video loss occurred or the time periods during which no recording schedule existed.

- 3) Select a time period and a status (exception or all) from the drop-down lists respectively to filter data.
- 4) **Optional:** Select the number of records displayed on each page of the History Recording Status panel from the drop-down list at the lower-left corner of the panel.
- 5) **Optional:** Move the cursor to the time bar to show the 24 hours on it, and click one hour to view recording status details within the hour.

istory Reco	rdi	ng Status	From the Very B	All	1
Time	1	Recording Status		t	Stora
2019/08/01					Main Sto
2019/08/02			35 40 45 50 55 00		Main Sto

Figure 27-19 Recording Status Details within One Hour

9. Optional: Click **Export** and then select a file format (i.e., Excel or CSV) to download the recording status as a single file to your local PC.

Chapter 28 Tools

The Control Client provides multiple tools: Smart Wall, Arming Control, Video Intercom, VSPlayer, Two-Way Audio, Broadcasting, Alarm Output.

Smart Wall

Play the live view or playback on smart wall. See *Manage Smart Wall (Decoding Device)* for details.

Arming Control

Arm or disarm the hot spots via the arming control function. After arming the device, the current Control Client can receive the triggered alarm information from the hot spot.

Video Intercom

Call the person's related indoor station.

VSPlayer

Run the player and play the video files stored on the local PC.

Two-way Audio

Enable the voice talk between the Control Client and devices, See <u>*Perform Two-Way Audio*</u> for details.

Broadcast

Distribute audio content to the added device if the device has an audio output. See <u>Broadcast</u> to <u>Connected Devices</u> for details.

Alarm Output

Enable alarm output to control the connected external devices by events or alarms, or manually by client. See *Control Alarm Output* for details.

28.1 Play Video via VSPlayer

You can run the VSPlayer software and play the video files stored in the local PC via the software.

Perform this task when you need to play video via VSPlayer.

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow$ **Tool** \rightarrow **VSPlayer** to run the VSPlayer.
- The available video files are listed on the playlist.
- 2. Double-click the video to play.
- **3. Optional:** Click in the upper-right corner of the VSPlayer page and select **User Manual** to view the VSPlayer's user manual for more detailed operations.

28.2 Perform Two-Way Audio

The two-way audio function enables the voice talk between the Control Client and devices. You can get and play not only the live video but also the real-time audio from the device in the Control Client, and the device can also get and play the real-time audio from the Control Client.

Perform this task when you need to perform the two-way audio function.

iNote

This function is not supported by the devices added in remote site.

Steps

- In the top left corner of Control Client, select Tool → Two-Way Audio to open the Two-Way Audio window.
- **2.** Select the camera in the area.
- 3. Select Device Talk or IP Talk.

Device Talk

Start two-way audio with the device (camera, NVR, DVR, or entrance/exit station).

i Note

- When the selected camera is directly connected to the system, the audio goes between the system and the camera.
- When the camera is connected to the system via an NVR, DVR, or entrance/exit station, and you select **Device Talk**, the two-way audio goes between the system and the NVR, DVR, or entrance/exit station.

IP Talk

Start two-way audio with the camera.

i Note

- When the camera is directly connected to the system, IP Talk can not be selected.
- When the camera is connected to the system via an NVR, DVR, or entrance/exit station, and you select **IP Talk**, the two-way audio goes between the camera and the system.
- 4. Click Start to start the two-way audio.
- **5. Optional:** Click (a) to adjust the microphone volume, click (a) to adjust the speaker volume, and click (e) to start recording.

28.3 Broadcast to Connected Devices

Perform the broadcast function to distribute audio content to the added device if the device has an audio output.

- Make sure the PC has available microphone for broadcasting audio to the device.
- If the client is performing two-way audio with the device's camera, you cannot start broadcasting with the device, and vice versa.
- The Cloud P2P device supports broadcasting if it enables DDNS.
- 1. In the top left corner of Control Client, select $\blacksquare \rightarrow$ Tool \rightarrow Broadcasting \rightarrow By Device .
- 2. Select an existing device group or click 💼 to add a device group if needed, and then click Add to select the device(s) to broadcast to.
- 3. Start or stop broadcasting.

Start All	Click Start All to start broadcasting to the selected device(s).
	Note
	You can view the real-time broadcast status.
Stop All	Click Stop All to stop broadcasting to the selected device(s).

28.4 Control Alarm Output

An alarm output is an output on the device that can be connected to an peripheral device, such as a light, a barrier, etc. Device can send signal to control the connected external device, e.g., turn on light, open the barrier gate. The connected peripheral device can be controlled automatically by events or alarms, or manually by client, and here we introduce the process for controlling alarm output remotely by client.

In the top left corner of the Control Client, select $\square \rightarrow$ Tool \rightarrow Alarm Output Control. Select the alarm output(s) that you want to enable/disable and click **Open/Close** them one by one. Or you can click **Open All/Close All** to enable/disable all alarm outputs.

28.5 Record Screen

You can record the PC screen and save the footage as evidence.

Steps

- **1.** In the top left corner of the Control Client, select $\blacksquare \rightarrow$ **Tool** \rightarrow **Record**.
- 2. Select the screen you want to record.
- 3. Click Start Recording.
- 4. Click Stop Recording.
- 5. Perform the following options.
 - Click **Save as...** to save the video as evidence.
 - Click **Open Folder** to open the folder which the record is saved to.

iNote

For details about setting the required information for evidence, see <u>Save Found Video Footage</u> <u>as Evidence</u>.

Chapter 29 System Settings

The System page contains general settings, basic video settings, alarm sound settings, health monitoring settings, screen position management, receipt printing settings, home page mode settings, and calling settings.

29.1 Set General Parameters

You can set the frequently-used parameters, including the network performance, display mode, file saving path, etc.

Steps

- 1. In the top left corner of Control Client, select → Management → System → General to enter the general settings page.
- 2. Configure the general parameters.

Network Timeout

The default waiting time for the Control Client. The operations will be regarded as failure if no response within the configured time.

The minimum default waiting time of the interactions between the Control Client and SYS server is 30s, the minimum time between SYS server and devices is 5s, and the minimum time between the Control Client and devices is 5s.

Maximum Mode

Select **Maximize** or **Full Screen** as the maximum mode. For selecting Maximize, the client will be maximized and the task bar will display. For selecting Full Screen, the client will be displayed in full-screen mode.

Time Zone

Device Time

The Control Client will adopt the time of the time zone where the device locates in.

Client Time

The Control Client (except the Video Analysis modules) will adopt the time of the time zone where the PC running the Control Client locates in.

Time Difference

If enabled, the time zone information will be displayed on the time. For example, 2018-12-12 12:12:12 +8:00.

Auto-Login

The system will remember the user name and password and log in to the Control Client automatically when you start the PC running the Control Client.

After Starting Client, Open

Automatically open the home page, last interface, or view after launching the client.

Home Page

Automatically display the control panel of the client after launching the client.

Last Interface

Restore the interface last opened when you run the client next time.

Specified View

Automatically display the specified view you set after launching the client.

INote

- You can click Show Screen No. to show the screen number of current PC running the Control Client. And you can select the specified view(s) according to your requirement. For details about setting view, refer to <u>Manage View</u>.
- Supports displaying the specified view on the auxiliary screen or on the smart wall (graphic card).
- For displaying on the smart wall (graphic card), you should set displaying contents on smart wall (graphic card) in smart wall mode. (See <u>Display Contents on Smart Wall in</u> <u>Smart Wall Mode</u> for details)
- For displaying on the smart wall (graphic card), when you select the specified view, the view should be displayed on the smart wall (graphic card) at the same time, and then the view will be displayed on the smart (graphic card) after launching the client next time, otherwise the view will be displayed on the auxiliary screen after launching the client next time.

Large-Scale Display Mode

To improve the resource operation efficiency, if there is one resource type with more than 512 resources, you can switch on **Large-Scale Display Mode**. In this mode, the resources in the system will not be loaded when launching the Control Client for time saving reason, so it will cost time when searching a device in the resource list.

iNote

- For the Central System in free version or with RSM (Remote Site Management) module, you cannot switch on the Large-Scale Display Mode. By default, the Central System in free version is in large-scale display mode, and the Central System with RSM module is in small-scale display mode.
- Areas without resources will be displayed and selecting all resources at a time is not supported.
- By default, the large-scale display mode is disabled.

File Saving Path

Set the saving paths for the files you downloaded to your computer (manual recorded or downloaded video files, captured pictures, and package files).

Report Auto Refresh Interval

Automatically refresh reports after the set interval to display the latest statistics. **3.** Click **Save**.

29.2 Set Video Parameters

You can set network parameters, picture file format, image parameters, people counting display parameters, icons on live view and playback toolbar, and shortcuts for keyboard and joystick.

29.2.1 Set Network Parameters

You can set global stream type for live view and window divisions for main stream.

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow$ Management \rightarrow System \rightarrow Video .
- 2. Select Network tab to enter network settings page.
- **3.** Configure network parameters.

Global Stream

Select the default stream type for live view for global usage. If the network is in good condition, select main stream or sub-stream. If the network is in poor condition, select smooth stream.

If the device doesn't support smooth stream, it will use sub-stream. If the device doesn't support sub-stream, it will use main stream.

If you don't want to adopt global stream settings for certain encoding device, you can go to **Maintenance** \rightarrow **Health Monitoring** \rightarrow **Encoding Device** and switch its stream type (refer to <u>**Resource Status**</u> for details). The Control Client will get this stream type to start live view of the encoding device's resources.

Window Divisions for Main Stream

When the number of divided windows is smaller than the number you set, the live video will be displayed by main stream.

Note

This parameter is invalid for playback.

Bandwidth

Set the bandwidth upper limit for downloading video from pStor server, which is used as a Recording Server for storing video files and pictures.

i Note

For details about adding pStor server as the Recording Server, see the User Manual of HikCentral Professional Web Client.

4. Click Save.

29.2.2 Set File Parameters

You can set the file format of pictures captured during live view and playback.

In the top-left corner of the Control Client, select $\square \rightarrow$ Management \rightarrow System \rightarrow Video \rightarrow File to enter the file settings page.

Select the file format for pictures captured during live view or playback.

Switch on Visual Tracking Video to automatically record the video during visual tracking.

iNote

When you use the visual tracking function for the first time, you will be prompted to select whether to automatically record the video during visual tracking. If you want to change the settings afterwards, you need to log in to the Control Client and switch on/off **Visual Tracking Video**.

Click **Save** to save the settings.

29.2.3 Set Display Parameters

You can set display parameters, including view scale, video caching, etc.

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow$ Management \rightarrow System \rightarrow Video .
- 2. Select Display tab to enter the display settings page.
- 3. Configure the display parameters.

View Scale

The image display mode in each display window in live view or playback.

Window Scale

The scale of the video in live view or playback. You can set it set as 4:3 or 16:9.

Display Window No.

Display the No. of each window in Monitoring module.

Display VCA Rule

When On, displays the VCA rule in the live view and playback.

Video Caching

Larger frame caching will result in better video performance. It is determined based on network performance, computer performance, and bit rate.

Continuous Decoding

Decode continuously when switching window division between one window and multiple windows.

Enable Highlight

Enable this function to mark the detected objects with green rectangles in live view and playback.

Overlay Transaction Information

When On, displays the transaction information on the live view and playback image.

]	i	Note
اس		inote

It is not supported when GPU hardware decoding is enabled.

Overlay Temperature Information

When On, displays the temperature information on the live view and playback image.

GPU Hardware Decoding

When On, enables the GPU decoding for live view and playback to save CPU resources. When the performance of the graphic card is good, you can enable GPU decoding to lower the computer's performance consumption. It is not recommended to enable this function if the graphic card's performance is poor.

i Note

- Your computer must support GPU decoding.
- After enabling GPU decoding, restart live view and playback for GPU decoding to take effect.
- If the client shows a blurred screen after enabling GPU decoding, disable GPU decoding.
- If GPU decoding is enabled, overlaying transaction information on live view and playback image is not supported.

Real-Time People Counting Display Configuration

Set the text overlaid on the real-time people counting window when the status is Allowed to Enter or Not Allowed to Enter. You can switch on **Bilingual** to enable bilingual text display and enter the second language text.

4. Click Save.

29.2.4 Set Audio Parameters

During playback, the audio of the video is turned off by default. You can set the audio parameters to automatically turn on the audio during video playback.

In the top-left corner of the Control Client, select $\blacksquare \rightarrow$ Management \rightarrow System \rightarrow Video \rightarrow Audio to enter the audio settings page.

Check Enable and click Save to enable this function.

You can also click **Default**, select **Current Page**, and click **OK** to restore the audio parameters to default settings.

29.2.5 Set Keyboard and Joystick Parameters

You can set shortcuts for the following hardware for quick and convenient access to the commonly used actions: PC keyboard, USB joystick, and USB keyboard.

Steps

- **1.** In the top left corner of Control Client, select $\blacksquare \rightarrow$ Management \rightarrow System \rightarrow Video .
- 2. Select Shortcut tab to enter the keyboard and joystick settings page.
- **3.** Select a function, and select the compound key number from the drop-down list to set it as the shortcut for the function.

Example

You can set **Backspace** key on the PC keyboard as the shortcut to stop live view. After that, you can press **Backspace** on the PC keyboard connected to the computer that runs the Control Client to quickly stop live view.

4. Click Save.

29.3 Set Linkage Action Parameters

You can customize the linkage information displayed in the Alarm Center by setting the linkage action parameters, including whether to display the related video, picture, or map, the priority content type to be displayed in the video window, and the default stream type for live view and playback.

In the top-left corner of the Control Client, select $\blacksquare \rightarrow$ All Modules \rightarrow Management \rightarrow System \rightarrow Alarm Center \rightarrow Linkage Action .

Select from the drop-down list to set the following parameters:

Display Linkage Information

The window(s) of the linkage information to be displayed in the Alarm Center. You can select to display the Related Video & Picture window, the Map window, or both for viewing the linkage information of an alarm.

Priority Display of Video Window

The priority content type to be displayed in the Related Video & Picture window.

For example, if you set **Priority Display of Video Window** to Related Picture, the captured picture of the alarm will be firstly displayed in the Related Video & Picture window in the Alarm Center.

IINote

This parameter is valid only when the **Display Linkage Information** is Display Related Video and Related Map or Display Related Video Only.

Default Stream Type of Linkage Video

The default stream type for live view and playback of the alarm in the Related Video & Picture window. By default, it is the sub-stream.

After setting the above parameters, click **Save** to save the settings.

29.4 Set Alarm Sound

When an alarm (e.g., a motion detection alarm, video exception alarm, etc.) is triggered, you can set the client to give an audible warning, and you can configure the sound of the audible warning for different priority levels.

Steps

- 1. In the top-left corner of the Control Client, select
 → Management → System → Alarm Center
 → Alarm Sound to enter the alarm sound settings page.
- 2. Select the alarm sound type.
 - If you select **Voice Engine**, the computer will play the voice text configured on the Web Client when the alarm is triggered.

INote

The Voice Engine function should be supported by the operating system of your computer.

- If you select Local Audio Files, perform the following steps:
 - a. Click 🗁 and select audio files from the local computer for different alarm levels.

i Note

- For configuring the priority level, refer to the User Manual of HikCentral Professional Web Client.
- The audio file can only be in WAV format.

b. Optional: Click 🔄 to test the audio file.

- **3. Optional:** Switch on **Play the Audio Repeatedly** and select the times of playing from the dropdown list.
- 4. Click Save.

29.5 Customize Icons on Alarm Center

You can customize the icons shown in the Operation column of the Alarm Center and adjust the icon order as needed.

Steps

- 1. In the top-left corner of the Control Client, select
 → All Modules → Management → System
 → Alarm Center → Alarm List .
- 2. Customize the icons shown in the Operation column of the Alarm Center.
 - Click an icon in the list to add it to the gray frame below to hide the icon. Icons in the gray frame will be hidden in the Operation column of the Alarm Center.

- Click the icon in the gray frame to add it back to show it in the Operation column of the Alarm Center.
- **3.** Drag the icons in the icon list to adjust the icon order.

•	View Linked Content	Start live view or playback of the related cameras of the alarm and view the captured pictures.
Ŷ	Two-Way Audio	Start two-way audio with the alarm source of the current site or the Remote Site.
a	Forward	Forward the alarm to other users for acknowledgment.
8	Ignore Alarm	Ignore the alarm so that the Control Client will not receive the alarm during the ignorance duration even though it is triggered.
a	Event & Alarm Search	Search alarms by setting conditions in the Event & Alarm Search page.
9	Export	Export the alarm details, including the alarm information, alarm picture, linked video, linked map, etc., to the local PC.
0	Disable Alarm	Disable the alarm so that the platform cannot receive and record the alarm during the disabling duration even though it is triggered.
	Display Alarm on Smart Wall	Display the alarm video on the smart wall. See <u>Manage</u> <u>Smart Wall (Decoding Device)</u> for details.

Table 29-1 Icons in Operation Column

The icons shown in the Operation column of the Alarm Center will vary with the device's capabilities.

4. Click Save to save the above settings.

What to do next

Restart the Control Client or switch users to apply the settings.

29.6 Set Health Status Parameters

You can configure the interval for automatically refreshing the resource status.

In the top-left corner of the Control Client, select $\blacksquare \rightarrow$ Management \rightarrow System \rightarrow Health Status to enter the health status settings page.

Select 30s, 1min, 3min, 5min, 10min, or 15min from the drop-down list to set as the auto-refresh interval.

Click Save.

29.7 Set Screen Position

For users adopting expanded screen during live view/playback or smart wall (graphic card), you need to set the screen position according to their real layout in order to switch screen by a network keyboard conveniently.

In the top left corner of Control Client, select $\blacksquare \rightarrow$ Management \rightarrow System \rightarrow Screen Position to display the current screen position on the right panel. You can hover the cursor on a screen to make sure the corresponding screens of the displayed windows. Drag a window to another window to change the relative position of the windows so that the controlling direction by joystick will also change.

29.8 Enable Printing Parking Free Receipts

You can enable printing parking receipts when the final charge is 0 for parking .

In the top left corner of Control Client, select $\blacksquare \rightarrow$ Management \rightarrow System \rightarrow Vehicle to enter the receipt printing settings page.

Switch on the **Print Receipt**.

In Print Receipt for Parking Free of Charge field, you can select **Print** or **Not Print** according to the actual need.

Click Save.

29.9 Switch Home Page Mode

The Home page can be displayed in Menu Mode and Visualization Mode. For Visualization Mode, the frequently used or important modules are displayed in a visual way via a control panel, and you can customize and arrange the modules on the control panel as you desired. For Menu Mode, all modules are displayed and arranged in a menu format on the Home page.

In the top left corner of Control Client, select $\square \rightarrow$ Management \rightarrow System \rightarrow Home Page Mode to enter the mode settings page.

Click a mode and click **Save** to switch the mode of Home page.

The settings will take effect after the Control Client is relaunched.

29.10 Set Ringtone for Calling

You can set ringtone for callings from access control devices, video intercom devices, and barrier gates in the parking lot.

In the top left corner of Control Client, select $\blacksquare \rightarrow$ Management \rightarrow System \rightarrow Calling to enter the ringtone settings page.

Switch on the Ringtone for Calling.

You can click to select an audio file from local PC, and click is to start playing the ringtone. Click **Save**.

